



Better Continents Guide

Updated edition for Valheim 1.0 and Better Continents 0.10.x

Originally written by billw2012 • maintained by Jere Kuusela

This edition: modified by Wubarrk, who now maintains Better Continents

Updated 22 September 2026 for Better Continents 0.8.0 and 0.8.1,

then 24 and 25 September and 2 October 2026 for 0.9.x,

and 4 and 5 October 2026 for 0.10.x

Based on JereKuusela/BetterContinents-Docs, commit 327106d (October 2025)

with the Better Continents source and the Valheim 1.0 game data

Licensed under the GNU General Public License, version 3. This edition is a modified version, released under the same license WITHOUT ANY WARRANTY. The license text is the final appendix; the Markdown source and build script are attached to this PDF (BetterContinents-Guide-1.0-edition-source.zip).

Contents

About this edition	8
How to read this edition	8
Better Continents 0.10.x	8
Sources, and how far they were checked	9
What changed, in brief	10
Which version is my world?	11
License	13
1 Introduction	15
Features	15
Additional Features	16
Useful Links	17
2 Quick Start	18
All players will need to follow at least the client part of the setup guide.	18
Then...	18
If you just want to play a world that someone else has created	18
If you want to improve on the vanilla world generation, but without making custom imagemaps	18
If you want to create your own world with maximum control over terrain and spawns.	18
Creating a world with your own maps	19
Tools	20
Painting colour maps	20
Template	20
3 Setup Guide	22
Client	22
Dedicated Server	22
IMPORTANT: You need to follow the Client setup guide as well!	24
4 Frequently Asked Questions	25
Where do I put downloaded worlds?	25
Where is my client log?	25
What are the image requirements for map files?	25
My world is all ocean, or much lower than I painted it. Why?	26
I edited my map images, but the world did not change.	26
The menu says Better Continents is DISABLED for my world.	26

Trees and rocks stand in pairs, a copy within a metre of each one. What is this?	27
A square of water looks deeper or shallower than the water around it. Why?	27
How big can a world be?	27

5 Image maps 28

5.1 Heightmap	29
Where to get Heightmaps	30
Creation Hints	30
Height scale and the waterline	31
Heightmap Amount	32
Heightmap Blend	33
Heightmap Add	34
Heightmap Mask	35
Heightmap Override All	35
Heightmap Alpha	35
5.2 Flatmap	36
Use Roughmap For Flatmap	36
Flatmap Blend	37
5.3 Roughmap	37
Roughmap Blend	39
5.4 Biome map	39
Biome precision	41
Expand World Data	42
Biomemap Creation Hints	43
5.5 Terrain map	44
Color mapping	45
5.6 Heatmap	45
Heat scale	46
5.7 Paint map	46
Moss and lava	46
5.8 Lava map	47
5.9 Moss map	47
5.10 Forest	47
Forest Scale	48
Forest Amount	49
Forest Factor Overrides All Trees	49
Forestmap Multiply	51
Forestmap Add	52
Recommended forest map settings	52
5.11 Location map	53

Image requirements	53
Behaviour	54
Creation Hints	55
5.12 Spawn map	55
Image requirements	55
Behavior	55
5.13 Vegetation map	57
Image requirements	57
Behavior	57
Doubled vegetation and bc_twins	58
6 Settings	59
BepInEx Configuration Manager	60
BepInEx Config File	60
Console Commands	62
Console command reference	62
The in-game settings window	65
6.1 Global	66
Enabled	66
Continent Size	66
Mountains Amount	67
Sea Level Adjustment	68
Ocean Channels	68
Rivers	69
Map Edge Drop-off	70
Mountains Allowed At Center	71
World Size	71
Edge Size	72
Ashlands Gap	73
Deep North Gap	73
Skip Default Locations	73
Fix Water Color	73
6.2 Project	73
Directory	73
6.3 Ridges	75
Max Ridge Height	75
Ridge Size	76
Ridge Blend	77
Ridge Amount	77
6.4 Height Layers	78
How layers combine	78

Commands	79
6.5 Start Position	80
Override Start Position	80
Start Position X	80
Start Position Y	81
6.6 Debug	81
Debug Mode	81
Skip Default Location Placement	82
Debug Reset Command	82
Override version	82
Zone regeneration	83
7 Alt Biomes	87
What alt biomes are	87
How Valheim assigns them	87
The cache file	89
The 32 alt biomes	89
What this means for map authors	92
Planting alt biomes with colours (BC 0.8.1)	93
Setting up the alt-biome map	93
The legend	93
Which pixels are planted	94
Default palette	95
What planting does	96
Modes	97
Controls for random placement	98
Reports and commands	99
Limits	101
Compatibility	101
8 Export and Import	102
Exporting the world you are in	102
Importing an export	103
Config that applies while the game runs	103
Biome precision	104
Joining a Better Continents world: the download, and how to shorten it	104
Compact Maps (experimental)	104
The full walkthrough	105
Appendix A Changes in this edition	106
BC 0.10 update (2026-10-04)	106

New worlds	106
Every world	107
Corrections to earlier edition text	108
The edition	109
BC 0.9.4 update (2026-10-02)	109
BC 0.9.1 update (2026-09-25)	109
BC 0.9.0 update (2026-09-24)	109
World export and import	109
Config that applies while the game runs	110
Joining a world: transfer rate and the shareable cache	110
Biome precision	110
BC 0.8.1 update (2026-09-22)	110
Maintenance, install and licence	110
Planting alt biomes (Alt Biomes chapter)	111
Colour tables and palette	111
The 0.8.1 fixes	111
Corrections to earlier edition text	111
Valheim 1.0.15 / BC 0.8.0 update (2026-09-22)	112
Whole guide	112
Introduction	112
Quick Start	112
Setup Guide	112
FAQ	113
Image maps	113
Heightmap	113
Flatmap	113
Roughmap	113
Biome map	113
Terrain map, Heat map, Paint map, Lava map, Moss map	113
Forest	114
Location map	114
Spawn map and Vegetation map	114
Settings	114
Global	114
Project	115
Ridges	115
Start Position	115
Debug	115
Minor corrections (not marked in place)	115

Appendix B Other images 116

Appendix C GNU General Public License, version 3 117

About this edition

Updated for Valheim 1.0 / BC 0.8.0: This page is new in this edition, and was brought up to date for BC 0.8.1, 0.9.x and 0.10.x. All of its text is edition text.

This is an edition of the *Better Continents Guide* (jerekuusela.github.io/BetterContinents-Docs, source repository JereKuusela/BetterContinents-Docs, commit [327106d](#), October 2025), brought up to date for **Valheim 1.0** and **Better Continents 0.10.x**. The guide was originally written by **billw2012** and is maintained by **Jere Kuusela**; the repository is a fork of billw2012/BetterContinents-Docs. This edition was prepared by Wubarrk, who now maintains Better Continents. It keeps the original structure, wording and images, and corrects or extends them only where the game or the mod has changed. It is licensed under the GNU GPL, version 3; see [License](#).

How to read this edition

- Boxes labelled **Updated for Valheim 1.0 / BC 0.8.0** are edition text. Everything outside those boxes is the original text, unchanged apart from the few corrections listed in [Changes in this edition](#).
- Boxes labelled **New in BC 0.8.1** describe what Better Continents 0.8.1 adds or fixes. What this edition says about BC 0.8.0 also holds for 0.8.1, unless a *New in BC 0.8.1* box says otherwise.
- Boxes labelled **New in BC 0.9.0** describe what Better Continents 0.9.0 adds or fixes: world export and import, the export HUD, config that applies while the game runs, and Biome precision. What this edition says about BC 0.8.1 also holds for 0.9.0, unless a *New in BC 0.9.0* box says otherwise.
- Boxes labelled **New in BC 0.9.4** describe the 0.9.4 change this edition covers: a world created *From Config* whose **Directory** is a world export takes that export's own settings.
- Boxes labelled **New in BC 0.10** describe what Better Continents 0.10 adds or changes. Every existing world and preset keeps its terrain, biomes and locations in 0.10 exactly as in 0.9.4: what these boxes describe is for **new worlds**, worlds of settings version 12, which is what 0.10 gives a world it creates, unless a box says it applies to every world. An *older world* is a world of version 11 or older: every world made before 0.10, and a world made in 0.10 as version 11. [Which version is my world?](#), below, says which is which.
- The chapters [Height Layers](#), [Alt Biomes](#) and [Export and Import](#), this page, the [License](#) page and the appendices are new; all of their text is edition text, except the licence text itself, which is reproduced verbatim.
- The site's console animations were recorded with an older Better Continents. In this PDF each is shown as four evenly spaced frames. The commands typed in them use the old `bc param ...` form, which no longer exists.
- The printed table of contents, the PDF bookmarks and the cross-references are all clickable.

Better Continents 0.10.x

- Better Continents was created by billw2012 and maintained by Jere Kuusela. **Wubarrk now maintains Better Continents.**
- Install** it from its Hexium page, valheim.hexium.gg/mods/Wubarrk/BetterContinents, for example with the Gale mod manager.
- Source code:** github.com/RGLabs84/BetterContinents10, where each release is tagged.
- This edition covers **Better Continents 0.10.x. 0.8.0** brought Better Continents to Valheim 1.0. **0.8.1** added planting alt biomes with colours, per-world control over the game's random alt-biome

placement, and commands to inspect it, and fixed Expand World Size worlds, in-game map edits not reaching the alt-biome grid, Deep North weather at sea, land beyond 10,500 m with the map edge drop-off off, and locations that accept several biomes. **0.9.0** added exporting the world you are in to a set of maps and importing an export (or any folder of maps) as a New World preset or your config, an in-game export HUD, config that applies while the game runs, and working Biome precision. See [Export and Import](#). **0.10** makes a new world's size real (World Size lays out the whole world), makes Heightmap Alpha work and Biome precision reach 2 m, works with more of Expand World Data, keeps doubled vegetation out of every world, holds maps in far less memory (with an experimental setting that keeps them compressed), regenerates the world's zones itself after each **bc** change, and makes the water of a zone follow its ground when the ground is rebuilt in place. Every existing world keeps its terrain, biomes and locations exactly as in 0.9.4.

- Target: Valheim 1.0, the current Steam build; the mod is rebuilt and re-verified for each game update without a new guide. The package depends on [denikson-BepInExPack_Valheim-5.4.2350](#).

Sources, and how far they were checked

In order of authority:

1. **The BC 0.8.0 source code and its documents** (README, the [MIGRATE-1.0.md](#) port record and the release changelog). Setting names, defaults, ranges and console commands in this edition were read from the code, not from older documentation.
2. **Facts established while building and play-testing test maps for 0.8.0:** the height scale and waterline, when the config is read, the world-creation preset, heat and forest map behaviour, and the 1.0 save layout.
3. **The Valheim 1.0 game code and data**, for the alt biome chapter. The list of alt biomes was extracted from the game's asset bundles.
4. **The Better Continents 0.8.1 source code, its alt-biome reference ([ALTBIOMES.md](#)) and its release changelog**, for planting alt biomes, the alt-biome controls and the 0.8.1 fixes. Config keys, commands, defaults, modes and file names are exactly as that reference gives them, and the colour tables are generated from the palette file that Better Continents generates from its own code.
5. **The Better Continents 0.9.0 source code and its release changelog**, for world export and import, the export HUD, config that applies while the game runs, and Biome precision. Config keys, commands, defaults and file names in [Export and Import](#) and this page were read from the code ([WorldExport.cs](#), [WorldImport.cs](#), [ExportHud.cs](#), [LiveConfig.cs](#), [Patcher.cs](#)), not from older documentation.
6. **The Better Continents 0.10 source code and its commit history**, for everything marked *New in BC 0.10*. Setting names, sections, defaults, ranges and descriptions were read from [SettingsSchema.cs](#), which declares every setting once; console commands from [DebugUtils.cs](#), [ConsoleTools.cs](#) and [VegetationTwins.cs](#); the export's text, formulas and files from [WorldExport.cs](#); what zone regeneration keeps and resets from [ZoneReset.cs](#) and [ZoneRegen.cs](#); and which behaviours belong to new worlds from the settings version gates in [Serialize.cs](#).

The port record is candid about what has and has not been exercised in play:

- **Verified in play:** creating a world from a full set of image maps on the Valheim 1.0 client with every location placed; the 1.0 save layout on new and upgraded worlds; upgrading a real pre-1.0 BC world; repeated saves; the minimap; booting on a real Valheim 1.0 dedicated server.
- **Not yet exercised in play:** BC's handling of Valheim's save operations (rename, copy, move and backup of a world, so keep your own backups) and the new Deep North weather and calm-sea handling. A dedicated server still cannot create a BC world by itself (see the [Setup Guide](#)).

- **BC 0.8.1:** its alt-biome code passes an offline test program that runs it against the real Valheim 1.0 game code, including real 0.8.0 worlds, whose settings must save byte for byte as 0.8.0 saves them, and planting has been shown working on a real Valheim 1.0 dedicated server.
- **BC 0.9.0:** when this edition first covered it (24 September 2026), world export, import, the export HUD, live config and Biome precision built cleanly and passed an offline test suite, including a byte-identical comparison of Biome precision's terrain builder against vanilla's, but had not run in a game; they have been in released builds since. See [Export and Import](#).
- **BC 0.10:** read from the source code and checked by the mod's offline test suites: reference tests that record what existing worlds do (and keep every one of them the same), and suites for the world layout, the map tiles, the twin guard, Heightmap Alpha, the Expand World Data rules, the export and zone regeneration. This edition marks only what it has seen in play; the rest of what it says about 0.10 comes from the code and those suites.

Where this edition describes behaviour that was read from source code and has not been seen in play, it says so.

What changed, in brief

- **Console:** open it with **F5**. The syntax is `bc <group> <setting> [value]` (for example `bc g sl 0.55`); there is no `param` level. `bc` is a cheat command. See [Settings](#).
- **Creating a world:** set the preset dropdown next to the seed to **From Config**, or BC ignores your config for that world. The config is baked into the world when it is created (since BC 0.9.0 the file is read again whenever it changes). See the [Quick Start](#).
- **Heightmaps:** the waterline is heightmap value 0.30 at the default Heightmap Amount of 1, and white is 140 m above water. See [Heightmap](#).
- **Removed or legacy:** Mountains Amount, Ocean Channels, Ridges and the Flatmap do nothing on new worlds (and since 0.10 Ocean Channels and Fix Water Color are gone from the config). Procedural terrain now comes from [Height Layers](#).
- **New settings:** World Size, Edge Size, Ashlands Gap, Deep North Gap, Skip Default Locations, Heightmap Mask, Heightmap Override All, Heightmap Alpha, Heatmap Scale, Debug Reset Command and more. See [Global](#), [Heightmap](#) and [Debug](#).
- **Deep North** is a real biome in Valheim 1.0, and BC 0.8.0 moves its weather and calm sea with the biome map. BC 0.8.1 also makes Deep North weather at sea follow the map.
- **Saves:** a 1.0 world is a folder, `worlds_local/<name>/`, and BC's settings live inside it in an extension-less file named `BetterContinents`.
- **Fixes:** a biome map that leaves out a biome no longer hangs world creation, and the minimap draws each biome correctly again.
- **Alt biomes:** Valheim 1.0 layers 32 biome variants onto regions of your map. The [Alt Biomes](#) chapter explains how they are assigned and what that means for map authors.
- **New in BC 0.8.1:**
 - **Planting alt biomes:** paint an alt-biome map to put chosen alt biomes on chosen regions, and steer or switch off the game's random placement. See [Planting alt biomes with colours](#).
 - **Expand World Size:** a world smaller than 10,500 m no longer crashes (EWS issue #26), and larger worlds map alt-biome regions correctly. See [Global](#).
 - **In-game map edits** now rebuild the alt-biome grid and the biomes of terrain chunks at once. See [The cache file](#), which also explains why the game never keeps a stale grid across loads.

- **Deep North weather:** on worlds with a biome map, Deep North weather at sea now follows the map. See [Biome map](#).
- **New in BC 0.9.0:**
 - **Export and import.** `bc_export` writes the world you are in to a folder of maps that rebuild it; `bc_import` (or a New World preset the export makes for you) turns such a folder back into a world, as a preset or through the config. See [Export and Import](#).
 - **Config that applies while the game runs.** `BetterContinents.cfg` is read again whenever it changes, not only once at launch, so an edit reaches the next world you create without restarting the game. See [Export and Import](#).
 - **Biome precision works again,** from 0 (vanilla) to 5 (a corner every 11 m): ground texture, grass, vegetation and spawn points follow your biome map inside each 64 m terrain zone; heights are unaffected. See [Biome map](#).
- **New in BC 0.9.4:** a world created *From Config* with **Directory** set to a world export now takes the export's `export.cfg`, so its heightmap is no longer read at the wrong Heightmap Amount and drowned. See [Project](#).
- **New in BC 0.10:**
 - **Every existing world keeps its terrain, biomes and locations as in 0.9.4.** What is new is for **new worlds** (settings version 12) unless it is marked as for every world ([Which version is my world?](#)).
 - **World Size lays out the world.** A new world's maps, alt-biome grid, locations, biome bands, Ashlands and Deep North rings, rivers and minimap follow its World Size and Edge Size. See [Global](#).
 - **Heightmap Amount 1 everywhere,** the world export's default included, with the Amount recorded inside an exported `heightmap.png`. **Heightmap Alpha** works on new worlds. See [Heightmap](#).
 - **Finer detail:** [Biome precision](#) up to 31 (cells of 2 m), location pins exactly on their pixels, the start position placed before the pins, and Start Position X and Y up to $\pm 1,000,000$ m.
 - **Expand World Data:** its altitude rules, lava biomes, terrain legend names, territory ground colours and biome names work with a Better Continents world. See [Biome map](#).
 - **In every world:** doubled vegetation is kept out, and `bc_twins` removes what a world already has ([Vegetation map](#)); maps are held as tiles in far less memory; the console tools answer the admin on a dedicated server; Better Continents regenerates the world's zones itself after each `bc` change ([Debug](#)); and the water of a zone follows its ground when the ground is rebuilt in place ([FAQ](#)).
 - **Experimental:** [Compact Maps](#) keeps a new world's maps compressed in memory and in the world file.

Which version is my world?

New in BC 0.10: Every world stores a *settings version* in its `BetterContinents` file, and Better Continents 0.10 follows the rules of that version. A world made by 0.9.x is **version 11**: it plays by the 0.9.4 rules and is saved as 0.9.4 saved it. The **new worlds** that this edition describes are **version 12**, which is what 0.10 gives a world it creates, but not every world made in 0.10 is one:

- **Read it.** `bc info` (console, **F5**; it needs `devcommands` and runs on the host; on a joined player's machine, where Server Devcommands lets it run, it shows the settings the server sent) prints `Version 11` or `Version 12` first. A world with no `BetterContinents` file in its folder is a vanilla world: `bc info` says `DISABLED`, and it has no version.
- **The four presets that ship with the mod** (Continents, Pangaea, Swirls and Vanillaish) are old **version 7** presets, so a world made from one is a **version 11** world. A preset you saved with 0.9.x makes a version 11 world too; one saved by 0.10 from a version 12 world makes a version 12 world.

- **A world made from an export** (the export's own preset, `bc_import`, or a Directory that holds an `export.cfg`) is version 12 when the export's maps span what its own World Size and Edge Size give: an export of a version 12 world, or of a 0.9.x world of the normal size. An export of a world that was resized under 0.9.x, or made under Expand World Size at another size, is version 11 and gets none of the new-world changes. See [Project](#).
- **A world as 0.9.4 would have made it**, on purpose: set **Override version** to `11` before you create the world with **From Config**, and empty the setting again afterwards. See [Override version](#).
- **Nothing converts an existing world** from version 11 to 12.

The Better Continents README sets this out in full, with a table of what each version does, in its section *Upgrading from 0.9: existing worlds and new worlds*.

[Changes in this edition](#) lists every substantive update.

License

Updated for Valheim 1.0 / BC 0.8.0: This page is new in this edition.

The *Better Continents Guide* is licensed under the **GNU General Public License, version 3** (GPL-3.0). It was originally written by billw2012 and is maintained by Jere Kuusela, at github.com/JereKuusela/BetterContinents-Docs, a fork of github.com/billw2012/BetterContinents-Docs.

This edition is a modified version. Its modifications, all by Wubarrk:

- **2026-09-22:** updated for Valheim 1.0.15 and Better Continents 0.8.0.
- **2026-09-22:** updated for Better Continents 0.8.1: planting alt biomes with colours, the alt-biome controls and reports, the 0.8.1 fixes, the colour tables and palette, and the install and source links now that Wubarrk maintains Better Continents.
- **2026-09-24:** updated for Better Continents 0.9.0: a new chapter, [Export and Import](#), for world export and import, the export HUD and config that applies while the game runs; and Biome precision, working again, noted in [Biome map](#).
- **2026-09-25:** rebuilt as the Valheim 1.0 / Better Continents 0.9.x edition after the Valheim 1.0.16 update: the game is named as Valheim 1.0 and the mod as 0.9.x wherever the edition states what it covers, so later patch releases of either do not need a new edition.
- **2026-10-02:** updated for Better Continents 0.9.4: a world created with *From Config* whose Directory is a world export takes that export's own settings, noted in [Project](#), [Export and Import](#) and the [FAQ](#).
- **2026-10-04:** rebuilt as the Valheim 1.0 / Better Continents 0.10.x edition: what 0.10 changes for new worlds and for every world (World Size that lays out the world, Heightmap Alpha, finer Biome precision, exact location pins, Expand World Data rules, Heightmap Amount 1 everywhere, the vegetation twin guard and `bc_twins`, maps held as tiles with the experimental Compact Maps, zone regeneration after `bc` changes, water that follows rebuilt ground, console tools), and corrections to earlier edition text.
- **2026-10-05:** revised the 0.10.x edition: which settings version a world has, how to tell, and how to make a world as 0.9.4 would have ([About this edition](#) and [Debug](#)); the four built-in presets named as version 7 presets; "older world" and "new world" used wherever a rule follows the settings version; and the statements on the vegetation twin guard, zone regeneration (which comes with the `bc` commands, not with Debug Mode), Heightmap Alpha, Override version, which worlds are version 11 (every kind listed), World Size, the Expand World Data lava biomes, the console ranges, what Debug Mode does, what `bc regen` rebuilds, the ground of the zones that regeneration keeps and where `bc` can be run corrected to what the code does.

The modifications are marked in place with *Updated for Valheim 1.0 / BC 0.8.0*, *New in BC 0.8.1*, *New in BC 0.9.0*, *New in BC 0.9.4* and *New in BC 0.10* boxes, and are listed in [Changes in this edition](#). The unmodified original is the repository above at commit [327106d](#).

This edition is released under the same license, the GNU General Public License, version 3. It is distributed **WITHOUT ANY WARRANTY**; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. The full text of the license is reproduced in the final appendix, [GNU General Public License, version 3](#).

Source code of this edition. The Markdown source of this edition and the build script for this PDF are attached to this PDF as the file `BetterContinents-Guide-1.0-edition-source.zip`. Open your PDF viewer's attachments panel to save it. The attachment contains:

- the edited Markdown pages ([updated/docs/](#));
- the license ([LICENSE](#), also at [updated/LICENSE](#));

- the build script (`build_pdf.py`), which describes how to rebuild the PDF.

The original images are not included in the attachment, because they would make it far larger (about 167 MB). They are unchanged from github.com/JereKuusela/BetterContinents-Docs at commit `327106d`, in its `docs/images` folder. This edition adds no image files of its own. The four-frame sheets shown for the animations are generated from the original GIFs by the build script.

1 Introduction

Better Continents allows you to create custom Valheim worlds using image files to control terrain, biomes, and world generation.

Generated worlds can be shared by copying world files along with the `.BetterContinents` settings file.

Updated for Valheim 1.0 / BC 0.8.0: In Valheim 1.0 every world is a folder, `worlds_local/<world name>/`, and BC 0.8.0 keeps the world's settings inside that folder in a file named just `BetterContinents`, with no extension. To share a world, copy the whole world folder. The image maps are baked into that settings file, so the people you share with do not need the image files. See the [Setup Guide](#) and the [FAQ](#).

The mod must be installed by all players using the world.

Updated for Valheim 1.0 / BC 0.8.0: More precisely, when a world uses Better Continents, the server sends the world's settings to each player as they join and refuses players whose Better Continents version is different from its own. Everyone therefore needs the same BC version on the server and on every client.

Features

Following image files can be used to modify the world:

- **Heightmaps** - Set terrain elevation
 - **Flatmaps** - Add fine detail to terrain elevation
 - **Roughmaps** - Control biome-specific terrain roughness
- **Biome Maps** - Set biome distribution
 - **Terrain Maps** - Set terrain color, independently of biomes
 - **Heatmaps** - Set Ashlands heat distribution
- **Paint Maps** - Set custom ground textures
 - **Lava Maps** - Set Ashlands lava
 - **Moss Maps** - Set Mistlands moss
- **Forest Maps** - Set forest coverage
- **Location Maps** - Set specific location placements
- **Spawn Maps** - Modify creature spawns
- **Vegetation Maps** - Modify plant distribution

Updated for Valheim 1.0 / BC 0.8.0: Flatmaps only work on worlds created with old versions of Better Continents. For new worlds, fine procedural detail comes from [Height Layers](#) instead. Biome maps can place Deep North, which is a real biome in Valheim 1.0.

Additional Features

- Change [global scale](#) to adjust continent sizes
- Adjust [mountains amount](#) and [sea level](#)
- Control [forest scaling](#) for forest/clearing area sizes
- Set explicit [starting positions](#)
- Add [ridged heightmap layers](#) for more varied geography
- Export full world maps to PNG at any resolution

Updated for Valheim 1.0 / BC 0.8.0:

- Mountains Amount no longer exists, and the separate ridge settings are gone. Ridged terrain is now a preset of the [Height Layers](#), which stack any number of procedural noise layers with Photoshop-style blend modes and masks.
- On worlds created with 0.8.0, Continent Size only affects the height layers. See [Global](#).
- The PNG export is the console command `bc scr [resolution]` (default 2048).
- New in the settings since this guide was written: world size and edge size, the Ashlands and Deep North ocean gaps, and skipping the default location placement. See [Global](#).
- Valheim 1.0 also adds *alt biomes*, variants such as Dark Meadows or Bog Swamp that the game layers onto whole regions of your map. See [Alt Biomes](#).

New in BC 0.8.1: An **alt-biome map** plants chosen alt biomes on chosen regions, like the biome map does for base biomes. See [Planting alt biomes with colours](#).

New in BC 0.10: Every existing world and preset keeps its terrain, biomes and locations exactly as in 0.9.4. What is new applies to **new worlds**, worlds of settings version 12 ([Which version is my world?](#)), and each page says so where it matters:

- **World Size makes the world.** A new world's maps, alt-biome grid, locations, biome bands, Ashlands and Deep North rings, rivers and minimap follow its [World Size](#) and Edge Size.
- **Heightmaps.** Heightmap Alpha blends a heightmap with the game's own terrain ([Heightmap](#)), and Heightmap Amount is 1 everywhere, the world export's default included.
- **Finer detail.** [Biome precision](#) goes up to 31 (cells of 2 m), location pins land exactly on their pixels, and the start position can be anywhere in a bigger world.
- **Expand World Data.** Its altitude rules, lava biomes and ground colours work with a Better Continents world ([Biome map](#)).
- **In every world.** Doubled vegetation is kept out and can be removed with `bc_twins` ([Vegetation map](#)); maps are held in far less memory; Better Continents regenerates the world's zones itself after each `bc` change ([Debug](#)), and the water of a zone follows its ground when the ground is rebuilt in place; and the console tools answer the admin on a dedicated server.
- **Experimental.** [Compact Maps](#) keeps a new world's maps compressed.

[Changes in this edition](#) lists every change.

Useful Links

[Better Continents](#) on Nexusmods

Join the [Valheim Worlds discord](#) to get help, share progress or tips and tricks.

See maps people have shared on [Nexusmods.com](#) [here](#).

Updated for Valheim 1.0 / BC 0.8.0: More links:

- Wubarrk now maintains Better Continents. Install it from its [Hexium page](#).
- Source code: github.com/RGLabs84/BetterContinents10, where each release is tagged.
- Companion mods recommended by the Better Continents README: [Server Devcommands](#) (BC adds tab completion for its `bc` command when it is installed), [Upgrade World](#) (world maintenance commands, among them `zones_reset`, which resets zones so that they generate again), [Infinity Hammer](#) (for building into your terrain) and [TortalPortal](#) (for portal travel across your continents).

2 Quick Start

All players will need to follow at least the client part of the [setup guide](#).

Then...

If you just want to play a world that someone else has created

- The [setup guide](#) explains how to upload worlds to your server.
- That should be it.

If you want to improve on the vanilla world generation, but without making custom imagemaps

- [Watch an example](#) of using the non-image features to improve and customize worlds.
- Check out the [settings](#) to find out what the different config parameters do, and how to apply them using the console to a world, while in game.

Updated for Valheim 1.0 / BC 0.8.0: The video shows an older Better Continents. In BC 0.8.0, new worlds without image maps are shaped by the [Height Layers](#), and the four built-in presets (Continents, Pangaea, Swirls and Vanillaish) are ready-made examples of them. Pick one in the preset dropdown when you create the world (see below). Without a heightmap or height layers the terrain is vanilla, and Continent Size and Sea Level have no effect.

New in BC 0.10: The four built-in presets are old settings-version 7 presets, so a world made from one is a version 11 world, as in 0.9.4 ([Which version is my world?](#)).

If you want to create your own world with maximum control over terrain and spawns.

- For a working example examine [my example map](#) which includes the source Photoshop file as a separate download.
- [Watch an example](#) of using the non-image features to improve and customize worlds.
- To see an example of authoring a image maps from scratch see [this video](#) in which I use my [template file](#). Use the chapters to see different parts of the process I am using.
- To see how to take the exported image files from the previous step into the game, and create and verify the world see [this other video](#).
- Check out the [settings](#) to find out what the different config parameters do, and how to apply them using the console to a world, while in game.

Creating a world with your own maps

Updated for Valheim 1.0 / BC 0.8.0: This section is new in this edition. It is the workflow that works on Valheim 1.0.

1. **Install** Better Continents as described in the [Setup Guide](#). The Better Continents README also recommends the companion mods [Server Devcommands](#), [Upgrade World](#), [Infinity Hammer](#) and [TortalPortal](#).
2. **Put your maps in one folder** with the standard file names ([heightmap.png](#), [biomemap.png](#), [forestmap.png](#) and so on) and set the **Directory** setting to that folder. See [Project](#). Alternatively, set each map's file path separately.

New in BC 0.8.1: to plant alt biomes, add an alt-biome map, [altbiomemap.png](#), to the same folder. See [Planting alt biomes with colours](#).

3. **Set the config values** you need, such as Heightmap Amount, either in [BepInEx/config/BetterContinents.cfg](#) or in the in-game Configuration Manager (F1). Author heightmaps for the default Heightmap Amount of 1: the waterline is then heightmap value 0.30 (see [Heightmap](#)).

New in BC 0.10: a new world is made to its **World Size** and Edge Size, so your maps cover the square from $-(\text{World Size} + \text{Edge Size})$ to $+(\text{World Size} + \text{Edge Size})$: 21 km at the default sizes. Amount 1 spans -30 m to 170 m on the game's height scale, where the sea is at 30 m (60 m below the water to 140 m above it), and clips higher ground; for a map with taller mountains use Amount 2 (-30 m to 370 m, up to 340 m above the water) and set it before you create the world. See [World Size](#).

4. **Save the config file before you create the world.** Better Continents bakes the config values into a world when the world is created. Since BC 0.9.0 it reads the file again within a second of any change, so a saved edit counts for the next world you create. (In BC 0.8.0 the file was read once, when the game launched, and you had to quit and relaunch.)
5. **Create the world:** Start Game → New world. **Set the preset dropdown next to the seed to "From Config"**, then create the world. If the dropdown shows "Disabled" (its default) or another preset, BC ignores your config for that world. Choosing one of the built-in presets (Continents, Pangaea, Swirls, Vanillaish) creates a procedural world from that preset instead.

New in BC 0.10: the built-in presets are old settings-version 7 presets, so a world made from one is a version 11 world. A world made with **From Config** is version 12: to make a world from your own maps as 0.9.4 would have made it, set Override version to 11 before you create it. See [Which version is my world?](#) and [Override version](#).

6. **Check that BC is active:** with the menu open (Esc), or while waiting to respawn, the bottom of the screen shows *Better Continents v0.10.x: ENABLED for this world*, where 0.10.x is the version you run.
7. **Inspect the world:** open the console with F5, enable cheats with [devcommands](#), then run [bc info](#) (prints the world's settings), [bc locs](#) (counts placed locations and warns about missing bosses), [bc bosses](#) (pins bosses, the start temple and the trader on the map) and [bc scr](#) (saves a PNG of the map).
8. **Iterate:** image maps are baked into the world when it is created, so editing a PNG never changes an existing world. For a clean result, change the maps or the config and create a new world. On a test world you can also change settings in game with the [bc](#) commands (cheat commands: Debug Mode turns cheats on for you). Better Continents then regenerates the world's zones itself, apart from those near something a player built or worked, a tombstone, another player or you inside a dungeon, and each reset zone generates again with the new settings when somebody comes near ([bc regen](#) does the same on demand; see [Debug](#)). Zones that are not reset keep their old

locations and vegetation, but the ground of every zone follows the new settings, so make big height changes before you build, or away from what you want to keep.

9. **Share** the finished world by copying its folder (see the [FAQ](#)).

To reuse a world's settings for new worlds, run `bc savepreset <name>` in that world. The preset is saved with a map thumbnail in `<Valheim save folder>/BetterContinents/presets/` and appears in the preset dropdown.

Tools

I would recommend using Photoshop or [Krita](#) for authoring, NOT GIMP, as GIMP does not support [non-destructive editing](#) via layer effects. Krita is open source, and has a mostly identical layer effects system to Photoshop. If you have a tablet then it can help a lot in painting smoothly and organically. You could use [World Machine](#) or [Gaea](#) to either generate a new heightmap, or modify an existing one. The erosion effects alone can help you make the terrain a lot more realistic, and be a guide on river placement. You could also generate biomes using it, but I won't be going into that here (it is a complex subject and I have not investigated it in any depth).

Painting colour maps

New in BC 0.8.1: This section is new in this edition.

- **Palette file and colour chart.** The release package and the source repository's `palettes/` folder contain `BetterContinents.gpl`, a palette with the ten biome map colours and the 32 default alt-biome colours, and `altbiome-palette.png`, a printable chart of the same colours, grouped by base biome. The palette is in the GIMP palette format, which Krita also reads.
 - **GIMP:** open the Palettes dialog (*Windows > Dockable Dialogs > Palettes*), right-click in the list of palettes, choose *Import Palette...* and pick the file.
 - **Krita:** use *Settings > Manage Resources... > Import Resources* and pick the file, or the import button in the Palette docker's list of palettes (*Settings > Dockers > Palette*).
- **Turn anti-aliasing off** when you paint a colour map: the biome map, the alt-biome map, and the terrain, paint, location, spawn and vegetation maps. Use the pencil tool rather than a soft brush, fill without anti-aliasing, and select without antialiasing or feathering. A blended edge pixel is a colour of its own. On a biome map it snaps to the nearest biome, which can be a third biome; on an alt-biome map it is planted by the nearest entry or not at all; on the other colour maps it matches nothing.
- **Export** at the image's own size, without resampling or colour-profile conversion, both of which shift colours too.

Template

I recommend you use my [template file](#) as a starting point. It contains premade groups, with height, water, and biome layers already setup. The intended usage of the groups\layers is like so:

- Heightmap\Heightmap: this is your base heightmap, paint it, paste something in, however you want to create it. The mask should be white for land and black for water (we can call this a "land mask"). You can generate the initial land mask using Threshold on the heightmap.
- Heightmap\Water edge mask: this is intended for creating smooth transitions between water and land, i.e. avoiding cliffs. The mask should be white for water, black for land (we can call this the "water mask"). i.e. This mask is the inverse of the land mask, and you can create it just by copying the land mask, then applying color invert.

- **Biomes:** the rest of the layers are the biomes themselves. Just paint white into the mask to apply that biome. You can use soft brush/smudge etc and then apply threshold to the mask directly to get crisp edges back again (which is required for it to load correctly).
- **Reference:** this contains reference images. Its often useful to drop in the source map you are trying to recreate, then set it as semi-transparent so you can paint over/under it. For my Middle Earth map I also dropped in a reference image that showed the route followed by Frodo/Bilbo so I could mark it with waymarkers in the spawnmap.
- **Reference\Biome Key:** this is just a reference for the biome colors, you don't need it really as the layers are already set up.
- **Reference\Spawn Table:** this is the key for how colors map to what is spawned. Where the same color maps to multiple things which one is used will be randomly selected on world creation. I did this to simplify the spawnmap creation process, and make it easier to read visually. If there are some in there that should not be grouped then please raise in the comments.[*]**Spawn:** this is your primary spawnmap layer. I suggest you put the main spawns in here (starting point, bosses, trader), and then add extra layers for things of which there are many. e.g. a layer for buildings, one for waymarkers, etc. I suggest you paint them in using 3 radius pencil (or bigger if you want more randomness). Ensure the spawn areas don't touch each other.
- **Source:** this is a place for your source images. You should put them in here to start with, and never modify them, rather copy them when you need to. Its always useful to be able to reference the unmodified source directly.

Updated for Valheim 1.0 / BC 0.8.0: In the template, the "spawnmap" layer and the "Spawn Table" are what BC now calls the **location map** and its colour key; see [Location map](#). Today's *spawn map* is a different map, which controls creature spawns ([Spawn map](#)). In BC 0.8.0 biome map pixels are matched to the nearest legend colour, so slightly-off colours still load. Crisp edges still matter, though, because a blended edge pixel can snap to a third biome (see [Biome map](#)). Location map colours must still match exactly.

3 Setup Guide

Client

Ideally use [Vortex](#) to install, as it includes all the dependencies you need for this mod already.

Updated for Valheim 1.0 / BC 0.8.0: Wubarrk now maintains Better Continents. For Valheim 1.0, install it from its [Hexium page](#) with a mod manager such as Gale, which installs BepInEx along with it. The package depends on [denikson-BepInExPack_Valheim-5.4.2350](#). To install by hand, put the package's `BetterContinents.dll` in `BepInEx\plugins` as described below. The source code is at github.com/RGLabs84/BetterContinents10, where each release is tagged.

Otherwise do this:

1. **Backup your world saves.** Do it. Do it now! Backup your characters aswell while you are at it.
2. **Install BepInEx Valheim.**
3. **Install Better Continents** itself: place the `BetterContinents.dll` in the `BepInEx\plugins` directory.

Optional but recommended if you want to make new worlds yourself:

- **Install the BepInEx Configuration Manager.** This gives you UI in game for changing configuration, otherwise you will need to edit text files to change settings.
- **Install the SkToolbox.** This gives improved console behaviour that makes iterating on a new world a nicer experience.

Updated for Valheim 1.0 / BC 0.8.0: The Better Continents README recommends these companion mods:

- [Server Devcommands](#). When it is installed (version 1.51 or later), Better Continents registers tab completion for its `bc` console command.
- [Upgrade World](#), world maintenance commands, among them `zones_reset`, which resets zones so that they generate again. After you change world settings in game, zones that were already generated keep their old locations and vegetation until they are regenerated. Better Continents regenerates them itself after a `bc` change (see [Debug](#)), and Upgrade World works alongside it: if you write a console command such as `zones_reset start` in the *Debug Reset Command* setting, Better Continents runs that command instead.
- [Infinity Hammer](#), for building ruins, landmarks and settlements into your terrain.
- [TortalPortal](#), a portal overhaul with destination previews, favourites and server synchronisation, for travel across your continents.

Dedicated Server

1. **Stop your server.**

2. **Backup your world saves** on from server. Do it. Do it now!

How you access them depends on your provider, probably ftp. Download them locally and put them somewhere safe.

Each world should have a `.fwl` and `.db` file, and the default world is called **Dedicated**.

On Linux servers the world files should be found at `.config/unity3d/IronGate/Valheim/worlds`, on Windows servers at `%AppData%\..\LocalLow\IronGate\Valheim\worlds` (same as for Windows clients).

3. **Enable mods on your server** if they are not enabled already.

How to do this is highly dependent on your server provider: for instance some have a toggle on the server management page to "enable mods", which results in BepInEx (or a mod that comes with BepInEx, e.g. Valheim+) being installed and enabled for you. Alternatively you might need to set this up yourself, in which case you should follow [BepInEx server installation guide](#).

4. **Upload this mod** to the `BepInEx\plugins` directory on your server. Again this depends on your server provider, but probably you will do it by FTP. The `BetterContinents.dll` file should now reside in the `BepInEx\plugins` directory.

5. **Upload the world** you want to use that was created with Better Continents, perhaps one from [here](#), or one you created your self. Its possible to create a new world ON the server, but it is easier to do it locally as you can modify the configuration in game and test it first.

NOTE: Some providers don't allow any files other than `.fwl` and `.db` to be uploaded. This will not work, you must also upload the `.BetterContinents` file. Complain to your server provider, or switch to another one!

6. **Point your server at the world** you uploaded. How to do it depends on your server provider, there should be some mechanism to specify the World Name, or modify the command line of the server.

7. **Start your server again** and join it.

Updated for Valheim 1.0 / BC 0.8.0:

- **World files in 1.0.** A world is now a folder, `worlds_local/<world name>/`, inside the same `.../IronGate/Valheim/` save folder (`worlds` is the older and cloud location). The folder holds the game's `_main.N.fwl2`, `.db2`, `.chunks` and `.ok` files plus the chunk files, and BC 0.8.0 puts the world's settings in the same folder in a file called `BetterContinents`, with **no extension**. Back up, and upload, the **whole folder**. If your provider filters uploads by file extension, check that the extension-less `BetterContinents` file arrived. Without it the world loads as a plain vanilla world.
- **Creating the world on the server does not work with BC 0.8.0.** Better Continents only bakes its settings into a new world when the world is created from the client's main menu, so a world created by a dedicated server comes out vanilla. Create the world locally, test it, then upload the folder.
- **Older worlds.** A pre-1.0 Better Continents world (`<name>.fwl`, `<name>.db` and `<name>.BetterContinents` side by side) still loads. On its first save, Valheim converts it to the folder layout and BC 0.8.0 moves the settings into the folder. It keeps the old file, renamed `<name>.BetterContinents.pre10`, because that file holds the only other copy of the world's maps.
- **Save operations.** Valheim's own rename, copy, move and backup routines only carry the game's file types, so BC 0.8.0 patches them to carry the settings file too. That part has not yet been exercised in play, so keep your own backups of BC worlds.

IMPORTANT: You need to follow the [Client setup guide](#) as well!

Both client **and** server need the same version of Better Continents installed when running a Better Continents world.

However: you can join servers that don't have Better Continents installed without it interfering (it will just be disabled).

You can also join servers that have Better Continents installed, without having it installed yourself, *as long as the server runs a world that doesn't require it* (i.e. one created without it).

Updated for Valheim 1.0 / BC 0.8.0: On a Better Continents world, the server sends the world's settings (including the baked image maps) to each client as it connects. The client caches them in `<save folder>/BetterContinents/cache/`, so players never need the image files. A client with a different BC version, or without BC, is refused with a connection error. The versions must match exactly.

New in BC 0.10: Play a new world (version 12) with 0.10 on the server and on every client, as with any version. Better Continents 0.9 still opens one, but as an older world: its maps span 21,000 m whatever its World Size says, for one, and its next save writes the world as version 11, so 0.10 then treats it as made by 0.9. Copy the world folder first if you try it. A world made with the experimental [Compact Maps](#) setting cannot be read by Better Continents 0.9 at all (it would generate the terrain as vanilla, and leave the world's settings file alone); it sends its maps compressed, so players download less. On a dedicated server, `bc_export server ...` and `bc_twins server ...` answer the admin who ran them as well as the server's log. A world's World Size, if you set one, is part of the world's settings like the rest: the server and the clients read it from the world.

4 Frequently Asked Questions

Where do I put downloaded worlds?

These go in the **worlds** directory, found at `%AppData%\..\LocalLow\IronGate\Valheim`. Just copy this path into your explorer bar and hit enter, and it will take you there.

Updated for Valheim 1.0 / BC 0.8.0: In Valheim 1.0 local worlds live in **worlds_local** in the same folder (`%AppData%\..\LocalLow\IronGate\Valheim\worlds_local` on Windows, `~/.config/unity3d/IronGate/Valheim/worlds_local` on Linux), and each world is its own folder. Copy the whole world folder, including the extension-less **BetterContinents** file inside it. A downloaded pre-1.0 world (loose `.fwl`, `.db` and `.BetterContinents` files) is converted to the folder layout the first time it is saved.

Where is my client log?

It is called **Player.log**, and is found at `%AppData%\..\LocalLow\IronGate\Valheim`. Just copy this path into your explorer bar and hit enter, and it will take you there.

Updated for Valheim 1.0 / BC 0.8.0: Better Continents prefixes its log lines with `[BetterContinents]`. When a world is created or loaded it logs the world's full settings, the same output as the `bc info` console command.

What are the image requirements for map files?

All the image maps must be:

- Square (width the same as height)
- A power of two. This means the valid sizes are 1, 2, 4, 8, 16, 32, 64, 128, 256, 512, 1024, 2048, 4096 **only**.
- One of these formats: Png, Jpeg, Bmp, Gif, Tga, Png is **strongly** preferred as it gives the best combination of size and color representation for this system.

It is **not** necessary for all images to be the same format or size, you can mix and match.

Updated for Valheim 1.0 / BC 0.8.0: BC 0.8.0's image loader (ImageSharp) only checks that an image is square. The power-of-two rule is no longer enforced, although power-of-two sizes remain a sensible choice. On an older world (settings version 11), every map covers the same 21 km × 21 km square, from -10,500 m to +10,500 m on each axis, whatever the World Size setting. A 2048 px map is therefore about 10.25 m per pixel and a 4096 px map about 5.1 m per pixel. (A new world, version 12, covers its own size: see below.) The top of the image is north, and the centre of the image is the centre of the world.

New in BC 0.10: On a new world (version 12) the maps cover the world: from $-(\text{World Size} + \text{Edge Size})$ to $+(\text{World Size} + \text{Edge Size})$ on each axis, which is the same 21 km at the default World Size and Edge Size. With a larger World Size each pixel covers more of the world, so draw (or export) at a size that suits it. A map from a world export covers the span its `manifest.json` gives as `totalSize`.

My world is all ocean, or much lower than I painted it. Why?

Updated for Valheim 1.0 / BC 0.8.0: This question is new in this edition. Check the height scale first. At the default Heightmap Amount of 1, the waterline is heightmap value **0.30** (grey 77 of 255), not 0.15, and white is 140 m above water. Using 0.15 as the waterline drowns every lowland biome. Second, the config is baked into the world when the world is created. If you changed Heightmap Amount after that (or, in BC 0.8.0, while the game was running, because the file was only read at launch), the world was built with the old value. Create a new world with the value you want. See [Heightmap](#).

New in BC 0.9.4: A heightmap from a [world export](#) is stored for the Heightmap Amount the export's `export.cfg` sets (the exports of 0.9.x use Amount 2, waterline 0.15). Before 0.9.4, a world made *From Config* with only **Directory** set to an export folder ignored `export.cfg`, read the heightmap at the config's Heightmap Amount (1 by default) and came out almost all ocean. Since 0.9.4 such a world takes the folder's `export.cfg` itself. A `heightmap.png` copied to a folder without its `export.cfg` needs the Heightmap Amount and Sea Level Adjustment it was made for in your config. See [Project](#).

New in BC 0.10: An export made by 0.10 stores its heights for Heightmap Amount 1 (waterline 0.30) unless it was asked for another, and records the Amount and Sea Level inside `heightmap.png` as well as in `export.cfg`. A new world that reads such a heightmap at other values writes a warning to the log naming both, and `bc info` shows the record, so open `BepInEx/LogOutput.log` and search for *world export*. See [Heightmap](#).

I edited my map images, but the world did not change.

Updated for Valheim 1.0 / BC 0.8.0: This question is new in this edition. The image maps are baked into the world when it is created, so editing a PNG never changes an existing world. Create a new world. On a test world you can also pull the new image in with `bc reload`, and Better Continents then regenerates the world's zones itself, apart from those around something a player built or worked, a tombstone, another player or you inside a dungeon (`bc regen` does it on demand; see [Debug](#)). Where the locations go was decided when the world was created, though, and a reset zone builds its location again on the same spot, so a new world is the reliable way.

New in BC 0.8.1: `bc reload` and the other in-game map edits now also rebuild the game's biome grid, which decides terrain biomes and alt biomes. With 0.8.0 the grid kept following the old map until the world was loaded again. See [The cache file](#).

The menu says Better Continents is DISABLED for my world.

Updated for Valheim 1.0 / BC 0.8.0: This question is new in this edition. Either the preset dropdown next to the seed was not set to *From Config* (or to a preset) when the world was created, or the world folder has lost its `BetterContinents` settings file. The dropdown defaults to *Disabled*.

Trees and rocks stand in pairs, a copy within a metre of each one. What is this?

New in BC 0.10: The game can fill a zone with vegetation a second time over its own objects (a save put back together from mismatched files, a zone command of a world tool), and then every tree and rock is doubled. Better Continents 0.10 keeps new doubles out of every Better Continents world, and `bc_twins` finds and removes the ones a world already has: `bc_twins` counts them, `bc_twins remove` shows what a cleanup would delete, and `bc_twins remove confirm` deletes it (on a dedicated server, ask it with `bc_twins server ...`). Back up the world first. See [Vegetation map](#).

A square of water looks deeper or shallower than the water around it. Why?

New in BC 0.10: Each 64 m zone has its own piece of water, and it works out how deep the sea is under it once, when the zone loads. If the ground under it was rebuilt afterwards (by a change made with `bc`, by `bc reset`, or by a terrain edit that loads after its zone), the water kept the depth it had started with. A square of sea with straight edges then looked deep (dark and reflective) among shallow-looking water (clear, with the sea bed showing), or the other way round, and its waves were sized for the old depth. Better Continents 0.10 gives each zone's water the depth of its rebuilt ground, so the square no longer appears; a world without Better Continents is left as the game has it. Before 0.10, going about 300 m away and back, or logging out and in, loaded the zone again and showed it right.

How big can a world be?

New in BC 0.10: Set **World Size** (and **Edge Size**) in the config before you create the world: a new world (version 12) is laid out to that size, and its maps cover it. The practical maximum is a World Size + Edge Size of about **16,350 m**, because Valheim files every object beyond about 16.35 km from the centre under one shared sector. A bigger world takes longer and more memory each time it loads, on the server and on every client as it joins, and very large maps are easier on memory with the experimental [Compact Maps](#) setting. See [World Size](#).

5 Image maps

Better Continents allows you to control world generation using various image files. Each type of map serves a specific purpose in customizing your Valheim world.

The following image maps are available:

- **Heightmaps** - Control terrain elevation
- **Biome Maps** - Control biome distribution
- **Paint Maps** - Set custom ground textures
- **Forest Maps** - Control forest coverage
- **Location Maps** - Set specific location placements
- **Spawn Maps** - Modify creature spawns
- **Vegetation Maps** - Modify plant distribution

Updated for Valheim 1.0 / BC 0.8.0: Things that hold for every map in BC 0.8.0 (read from the source code):

- **Coverage and orientation.** Every map covers the same square, centred on the world centre: from -10,500 m to +10,500 m on each axis (21 km × 21 km) on an older world (settings version 11), whatever its World Size and Edge Size settings say. On a new world (version 12) the square is as large as the world: from -(World Size + Edge Size) to +(World Size + Edge Size), which is the same 21 km at the default sizes (see [Global](#)). The top of the image is north, the left edge is west, and the image centre is the world centre.
- **Baked at creation.** When a world is created, BC stores every map, together with the effect of its colour legend, in the world's **BetterContinents** settings file. Editing an image or a legend afterwards does not change that world.
- **Legend files.** The colour-keyed maps read a text legend named after the image, next to it: **biomemap.txt**, **terrainmap.txt**, **paintmap.txt**, **locationmap.txt**, **spawnmap.txt**, **vegetationmap.txt**. If the file is missing, BC writes one containing the defaults (empty for the paint, spawn and vegetation maps).
- **Where the settings live.** Map file settings are in the config sections **02 BetterContinents.Heightmap** (heightmap, roughmap), **03 BetterContinents.Biomemap** (biome map, terrain map), **04 BetterContinents.Forest** (forest map) and **06 BetterContinents.Maps** (location, spawn, vegetation, paint, lava, moss and heat maps). The Project [Directory](#) setting, if set, replaces all of these paths.
- **Reloading in game.** **bc reload <map>** re-reads an image from disk on the current world. The map names are **hm**, **rm**, **fm**, **bm**, **terrain**, **lm**, **fom**, **paint**, **lava**, **moss**, **vegetation**, **heat**, **spawn** and **all**. Only the maps the world actually uses are offered.

New in BC 0.8.1: There is one more map, the **alt-biome map** **altbiomemap.png**, which plants Valheim 1.0's alt biomes on the regions you paint. It has its own legend, **altbiomemap.txt**, and its settings are in the config section **08 BetterContinents.AltBiomes** (**Altbiomemap File** sets the file). In game, **bc reload ab** re-reads it, and **bc reload all** includes it. It is described in the Alt Biomes chapter, under [Planting alt biomes with colours](#).

Also new: after an in-game map edit or **bc reload**, Better Continents 0.8.1 rebuilds the world's biome grid as well, so terrain biomes and alt biomes follow the new map at once. See [The cache file](#).

New in BC 0.10: Maps are held as tiles. Every float, biome, spawn, vegetation, paint and terrain map keeps its pixels in tiles of 128×128 pixels, and a tile of one value (open sea, the canvas around a painted area) is held as that one value. Every value read from a map is exactly what it was and reading is as fast, but the memory is far smaller: for a real set of a 10,501 px heightmap, forest map and biome map, a world holds about 99 MB instead of about 1.32 GB. The files you make and the files a world saves do not change. The experimental setting [Compact Maps](#) goes further.

5.1 Heightmap

The heightmap allows direct control of the base height values for the whole map. It can blend with, or replace the base part of the vanilla procedurally generation.

A heightmap of 4096×4096 results in each pixel representing about 4×4 meters in game (the map size is $20 \text{ km} \times 20 \text{ km}$).


The cloud layer in game has been determined to be at about 400 m above sealevel, meaning that an 8 bit heightmap (256 gray levels) can represent height differences of about 1.5 m. A 16 bit heightmap can represent height differences of less than 1 cm.

Use 16 bit grayscale PNG for the heightmap.

Updated for Valheim 1.0 / BC 0.8.0: In BC 0.8.0 the image covers the full $21 \text{ km} \times 21 \text{ km}$ square (from $-10,500 \text{ m}$ to $+10,500 \text{ m}$ on each axis), so a 4096 px heightmap is about 5.1 m per pixel and a 2048 px one about 10.25 m per pixel (on an older world (settings version 11), or with the default World Size and Edge Size; see the next box). At the default Heightmap Amount of 1, the whole 0–1 range of the image spans 200 m of height (see [below](#)), so one 8-bit grey level is about 0.8 m. 16-bit is still the better choice.

New in BC 0.10: On a **new world** the heightmap covers the square from $-(\text{World Size} + \text{Edge Size})$ to $+(\text{World Size} + \text{Edge Size})$ on each axis, as every map does. With the default World Size (10000) and Edge Size (500) that is the same 21 km square, so the figures above stand. With another World Size the square, and the metres per pixel, change with it; an older world (settings version 11) keeps the 21 km square whatever its World Size says. See [Global](#).


Examples



example-hm.png



logo-heightmap.png



me-heightmap.png

ConsoleCommand: `bc h fn`

Updated for Valheim 1.0 / BC 0.8.0: Was `bc param h fn`; the `param` word no longer exists. The value can be a full path, a directory, or a file name that is looked up in the Project Directory. The animation was recorded with the old syntax.



Frames 1, 15, 30 and 44 of 44 from the original animation `bc-param-h-fn.gif` (15 s), left to right, top to bottom.

Where to get Heightmaps

- Craft them from scratch in some package. People have used Photoshop, Krita, GIMP, Blender to good affect.
- [Google](#)
- This very nice [Google Maps style page](#) that will export heightmaps directly for any area on Earth.
- [World Machine](#): This is highly advanced heightmap generating software that can do things like physical modelling of erosion. It can also generate assist in generating biome maps automatically as well.
- [Gaea](#): Similar to World Machine, might be quicker to get started with.

Creation Hints

- Ensure the ocean areas of the heightmap are pure black, not grey
- Apply automatic contrast/levels to ensure the values are using the full range available
- I recommend smoothing (blurring) the image to avoid any sharp changes in altitude
- Getting sealevel looking correct might take some tweaking, of either the image itself or the sealevel setting
- To determine sealevel with your current config settings you can create a smooth gradient on the heightmap (gradient paint bucket tool in Photoshop), apply a flatish biome to it (e.g. plains), and then view it in game to determine what gray value corresponds to sealevel. In my testing with sealevel set to 25% the corresponding gray value is about `#0d0d0d`.
- When trying to test your map in game start with all default, then set these settings:

- [Heightmap File](#) - paste your file name in here, or use the [Project Directory](#) with an appropriate heightmap file in it.
- [Ocean Channels](#) un-ticked
- [Rivers](#) un-ticked
- [Ridges Amount](#) 0%

Updated for Valheim 1.0 / BC 0.8.0: Corrections to these hints for new worlds:

- You no longer need to find the sea level by experiment: it can be calculated (next section). The #0d0d0d at 25% observation comes from an older height formula. With BC 0.8.0 a Sea Level of 0.25 puts even pure black 40 m above the water.
- Pure black is 60 m below the water at the default Heightmap Amount, which is fine for open ocean. Grade coasts and shallows up to the waterline value (0.30) rather than dropping straight to black.
- The test settings are no longer needed. Ocean Channels and Ridges do nothing on new worlds, and with Heightmap Override All on (the default) vanilla's rivers never appear. **Rivers and lakes must be carved into the heightmap itself.**
- Vanilla places many locations (bosses, traders, dungeons) by distance from the world centre, so a map keeps its locations when Meadows are central and the harsher biomes further out.
- Unless [Mountains Allowed At Center](#) is on, BC caps the terrain within about 600 m of the world centre at 46 m above the water, blending back to your heightmap by 1,000 m.
- Sanity-check a new map before playing it. Measure, per biome, how much of it lies above the waterline. If the lowland biomes (Meadows, Swamp, Plains) come out near 0 % above water, or only a metre or two above, the height scale is wrong and the world will be drowned, however good the map looks.

Height scale and the waterline

Updated for Valheim 1.0 / BC 0.8.0: This section is new in this edition. With a heightmap loaded and Heightmap Override All on (the default), BC 0.8.0 computes each point's height like this (Blend 1, Add 0 and Mask 0, the defaults):

```
finalHeight      = heightmapValue × HeightmapAmount - 0.15 + SeaLevelAdjustment
SeaLevelAdjustment = Lerp(1, -1, SeaLevel)    (0 at the default Sea Level, 0.5)
world height (m)  = finalHeight × 200         (water at 30 m = finalHeight 0.15)
```

So at the default Sea Level:

- the **shoreline** is heightmap value **0.30 / HeightmapAmount**;
- **metres above water = (value × HeightmapAmount – 0.30) × 200**;
- at the default Amount of 1.0, the waterline is value 0.30 (about grey 77 of 255 in an 8-bit image), white is **140 m above water** (the ceiling) and black is 60 m below.

Heightmap value	8-bit grey	Height at Amount 1.0
0.00	0	60 m below water
0.15	38	30 m below water
0.30	77	waterline
0.40	102	20 m above water
0.50	128	40 m above water

Heightmap value	8-bit grey	Height at Amount 1.0
0.75	191	90 m above water
1.00	255	140 m above water

Using 0.15 as the waterline at the default Amount is a real mistake that has been made: it puts every lowland biome up to 30 m under water, and the map renders as bare peaks in an empty ocean.

Sea Level moves the waterline to heightmap value $(2 \times \text{SeaLevel} - 0.7) / \text{HeightmapAmount}$. Each 0.05 of Sea Level is 20 m of water. At Amount 1, a Sea Level of 0.35 or less drains the sea completely, and 0.85 or more puts everything under water.

Author for the default Amount of 1.0. Heightmap Amount, like the rest of the config, is baked into the world when it is created. A map drawn for a different Amount is only right if the config held that value at that moment. When the ordering slips, the map is read against the wrong Amount; a map drawn for 1.6 and read at 1.0 came out entirely under water.

New in BC 0.10: Heightmap Amount 1 is the default everywhere: in the config, in the console, in the world export (which used to export at Amount 2) and when an export is imported. On the game's own height scale, where the sea surface is at 30 m, a heightmap at Amount 1 and the default Sea Level spans **−30 m to 170 m**: black is 60 m below the sea and white is 140 m above it. Ground higher than that cannot be drawn: it **clips** to white.

When Amount 2 is worth it. At Amount 2 a heightmap spans **−30 m to 370 m** (white is 340 m above the sea) and keeps every vanilla mountain. The price is coarser steps: one 8-bit grey level is about 1.6 m instead of 0.8 m, and one 16-bit level about 6 mm instead of 3 mm. Use it when your map has ground higher than 140 m above the sea, for example a heightmap that holds the game's own tallest mountains (a world export reports how many pixels it had to clip), and draw it for Amount 2: the waterline is then value 0.15. Set Heightmap Amount to 2 before you create the world.

Heightmap value	8-bit grey	Height at Amount 2.0
0.00	0	60 m below water
0.15	38	waterline
0.30	77	60 m above water
0.50	128	140 m above water
0.75	191	240 m above water
1.00	255	340 m above water

At any Amount and Sea Level, the height on the game's scale is $(\text{pixel} / 65535 \times \text{Heightmap Amount} - 0.15 + \text{Lerp}(1, -1, \text{Sea Level Adjustment})) \times 200$ metres, where **pixel** is the 16-bit grey value; subtract 30 for the height above the sea.

Heightmap Amount SETTING

Multiplier of the height value from the heightmap file (more than 1 leads to higher max height than vanilla, good results are not guaranteed).

Default **1**
Range **0** to **5**

Updated for Valheim 1.0 / BC 0.8.0: Heightmap Amount sets the altitude ceiling: $(\text{Amount} - 0.30) \times 200$ m above water, so 140 m at the default. It is baked in at world creation (see above).

New in BC 0.10: A world export writes the Heightmap Amount and Sea Level Adjustment its heights are encoded for into its `heightmap.png` itself, as a PNG text chunk named `BetterContinents` that reads, for example, `Heightmap Amount = 1; Sea Level Adjustment = 0.5` (image editors show it and often keep it). Nothing changes by itself: when a new world reads such a heightmap at other values, the log (`BepInEx/LogOutput.log`) carries a warning that names both pairs of values, and `bc info` shows the record. A heightmap without a record, such as every heightmap made before 0.10 and every one you draw yourself, is read exactly as before. See [Export and Import](#).

Console

Command: `bc h am`

Updated for Valheim 1.0 / BC 0.8.0: Was `bc param h am`. The animation was recorded with the old syntax.



Frames 1, 25, 49 and 73 of 73 from the original animation `bc-param-h-am.gif` (22 s), left to right, top to bottom.

Heightmap Blend SETTING

How strongly to blend the heightmap file into the final result.

Default **1**

Range **0** to **1**

Updated for Valheim 1.0 / BC 0.8.0: In the height function used by new worlds, the heightmap is blended against zero, which is flat ground 60 m below the water, so Blend works as a multiplier on the heightmap. To mix the heightmap with procedural terrain, use [Height Layers](#), which are applied on top of it.

Console

Command: `bc h bl`

Updated for Valheim 1.0 / BC 0.8.0: Was `bc param h bl`. The animation was recorded with the old syntax.



Frames 1, 27, 53 and 78 of 78 from the original animation bc-param-h-bl.gif (27 s), left to right, top to bottom.

Heightmap Add SETTING

How strongly to add the heightmap file to the final result (usually you want to blend it instead).


Default 0

Range -1 to 1

Console

Command: `bc h ad`

Updated for Valheim 1.0 / BC 0.8.0: Was `bc param h ad`. The animation was recorded with the old syntax.



Frames 1, 30, 60 and 89 of 89 from the original animation bc-param-h-ad.gif (31 s), left to right, top to bottom.

Heightmap Mask SETTING

Updated for Valheim 1.0 / BC 0.8.0: This setting is new in this edition's coverage. Config description: *How strongly to apply the heightmap as a mask on normal height generation (i.e. it limits maximum height to the height of the mask).* Default `0`, range `0` to `1`. Console: `bc h ma`.

Heightmap Override All SETTING

Updated for Valheim 1.0 / BC 0.8.0: This setting is new in this edition's coverage. Config description: *All other aspects of the height calculation will be disabled, so the world will perfectly conform to your heightmap.* Default `true`. Console: `bc h ov`.

When it is on, each point's height is taken straight from BC's height function: your heightmap plus any [Height Layers](#). Vanilla's biome-specific terrain shapes, vanilla's rivers and the [roughmap](#) are all bypassed. When it is off, vanilla's biome terrain (swamp flattening, mountain peaks, rivers and so on) is built on top of your heightmap, and the roughmap can blend between the two.

New in BC 0.10: With Expand World Data installed, a **new world** also applies that mod's altitude rules (a biome's or a territory's altitude multiplier and delta, water depth, height limits and lava dip) over the heights this setting gives. See [Expand World Data](#).

Heightmap Alpha SETTING

Updated for Valheim 1.0 / BC 0.8.0: This setting is new in this edition's coverage. Config description: *Enables alpha channel for the heightmap file to blend vanilla generation with the heightmap.* Default `false`. Console: `bc h alpha`. In BC 0.8.0 to 0.9.x the alpha channel was loaded but never used when heights were sampled and, with Heightmap Alpha on, the heightmap was read at 8 bits (heights in 256 steps), so the setting blended nothing and only made the heights coarser.

New in BC 0.10: Heightmap Alpha works on **new worlds**. Save the heightmap as a 16-bit grey PNG with an alpha channel, turn Heightmap Alpha on, and create the world:

- The heightmap is read at full 16-bit precision, with a 16-bit alpha.
- Where a pixel is opaque the world takes the heightmap's height; where it is transparent the game's own terrain shows (the terrain the world's seed would give without Better Continents); in between, the two blend by the alpha. So a heightmap can shape one region and leave the rest to the game.
- With [Heightmap Override All](#) on, each biome's height follows the blended height.
- `bc h alpha true` (or `false`) decodes the heightmap again at once, in every world: an older world re-reads it the old way (below). Before 0.10 a change did nothing until the world was loaded again.

An older world (settings version 11) reads the heightmap as it always did when Heightmap Alpha is on: as 8-bit grey with the alpha unused. With Heightmap Alpha off, every world reads it as 16-bit grey. `bc info` says which way a world reads it, in a line that appears only when the world has a heightmap and Heightmap Alpha is on.

5.2 Flatmap

Updated for Valheim 1.0 / BC 0.8.0: The flatmap is a **legacy feature**. BC 0.8.0 has no config setting and no console command for it, and the Project Directory does not load a `flatmap.png`. Only worlds whose settings are stored in an old Better Continents save format (formats 5 and 6) still use a stored flatmap, and on those worlds `bc reload fm` still reloads it. On new worlds, small-scale procedural detail comes from [Height Layers](#). The original description below is kept for reference.

The flatmap controls the smaller detail bumpiness that is applied ontop of the large scale height changes in the base height calculation. A black value in the flatmap will result in the vanilla small height variations being unmodified. A white value will result in them being removed entirely. As the roughmap and flatmap have similar but inverted behavior (they both serve to control small scale variations in height), you can use one of them to drive the other with the "Use Rough For Flat" flag in the config. This will use the roughmap (inverted, so white is black and vice versa) as the flat map. The means if you paint all black in roughmap it will remove all extra procedural details (excluding the Ocean Channels and Rivers, which you can also toggle in the config).

Use Roughmap For Flatmap SETTING

Use the flatmap as the rough map, but inverted (black rough map results in totally flat terrain).


Default true

Use 8 bit grayscale PNG of medium resolution for the flatmap.


Console

Command: `bc param f fn`

Updated for Valheim 1.0 / BC 0.8.0: This command no longer exists in BC 0.8.0 (there is no `f` group). The animation shows an older version.



Frames 1, 7, 13 and 18 of 18 from the original animation `bc-param-f-fn.gif` (6 s), left to right, top to bottom.



Flatmap Blend SETTING

How strongly to apply the flatmap file (also applies when using Use Roughmap For Flatmap).


Default **1**

Range **0** to **1**

Console

Command: `bc param f bl`

Updated for Valheim 1.0 / BC 0.8.0: This command no longer exists in BC 0.8.0. The animation shows an older version.



Frames 1, 26, 51 and 75 of 75 from the original animation bc-param-f-bl.gif (28 s), left to right, top to bottom.

5.3 Roughmap

The roughmap controls the strength of the vanilla biome specific heightmap variations. In vanilla each biome has its own additional height variation that is applied, for instance the swamp height is always set to about sea-level, mountains have extra large scale variation applied to generate peaks. A white value in the roughmap will result in the vanilla biome variations being unmodified. A black value will result in them being removed entirely.


Use 8 bit grayscale PNG of medium resolution for the roughmap.

Updated for Valheim 1.0 / BC 0.8.0: When a heightmap is loaded with **Heightmap Override All** on (the default), the terrain comes straight from the heightmap and the roughmap is ignored. Turn Override All off to use a roughmap with a heightmap. The roughmap settings (**Roughmap File**, **Roughmap Blend**) are in the config section **02 BetterContinents.Heightmap**.


Console

Command: `bc r fn`

Updated for Valheim 1.0 / BC 0.8.0: Was `bc param r fn`. The animations were recorded with the old syntax.



Frames 1, 8, 15 and 22 of 22 from the original animation `bc-param-r-fn.gif` (7 s), left to right, top to bottom.



Frames 1, 8, 16 and 23 of 23 from the original animation `bc-param-r-fn-2.gif` (7 s), left to right, top to bottom.

Roughmap Blend

SETTING


How strongly to apply the roughmap file.

Default 1
Range 0 to 1

Console

Command: `bc r bl`

Updated for Valheim 1.0 / BC 0.8.0: Was `bc param r bl`. The animation was recorded with the old syntax.



Frames 1, 21, 41 and 61 of 61 from the original animation `bc-param-r-bl.gif` (22 s), left to right, top to bottom.

5.4 Biome map

The biome map can be used to override the default biome generation.

Each biome is represented by a specific color. The biome Default can be used for the default biome generation.

Swatch	Biome	Hex	R, G, B
	None	000000	0, 0, 0
	Meadows	00FF00	0, 255, 0
	BlackForest	007F00	0, 127, 0
	Swamp	7F7F00	127, 127, 0
	Mountain	FFFFFF	255, 255, 255
	Plains	FFFF00	255, 255, 0
	Mistlands	7F7F7F	127, 127, 127
	AshLands	FF0000	255, 0, 0
	DeepNorth	00FFFF	0, 255, 255
	Ocean	0000FF	0, 0, 255

New in BC 0.8.1: This table is generated from Better Continents' palette file ([palettes/palette.json](#) in its source repository), in the palette's order and with the names the legend file uses: **None** is the *Default* above. The original guide's table showed the same colours, with the names Mountains, Ash Lands and Default; its colour chips are shown in [Other images](#).

The colors can be changed by editing the biomemap.txt file. This is required when using custom biomes from Expand World Data mod.

Use 32 bit RGBA PNG for the biomemap. For biomes, the file size doesn't matter because the actual biome values are stored instead of the image data.

Updated for Valheim 1.0 / BC 0.8.0:

- **The legend file** is named after the image and sits next to it (`biomemap.txt` for `biomemap.png`). If it is missing, BC writes it with the defaults. Each line is **Name: RRGGBB** (or **Name: r,g,b**):

```
None: 000000
Meadows: 00FF00
BlackForest: 007F00
Swamp: 7F7F00
Mountain: FFFFFFFF
Plains: FFFF00
Mistlands: 7F7F7F
AshLands: FF0000
DeepNorth: 00FFFF
Ocean: 0000FF
```

None is the *Default* of the text above: those pixels use the default (vanilla) biome generation.

- **Only the ten names above were accepted in BC 0.8.0 to 0.9.2.** Valheim 1.0 converts biomes to indices with a lookup that throws an error on any value it does not know. BC therefore rejected the whole legend and fell back to the defaults if it contained any other name, so custom biomes from Expand World Data could not be mapped. Since BC 0.9.3 the legend also accepts the names Expand World Data gives the biomes it adds (see [Expand World Data](#) below).
- **Pixels snap to the nearest legend colour**, so slightly-off colours still load. Keep edges hard (no anti-aliasing or soft brushes), because a blended edge pixel can snap to a third biome. A soft coastline between Meadows, Plains or Swamp and Ocean comes out as a thin fringe of **Mistlands**. For example, the half-way blend of Meadows and Ocean (0,128,128) is nearest to Mistlands.
- **Deep North is a real biome in Valheim 1.0.** Vanilla still decides where the Deep North's weather, snow painting and calm sea are by a fixed geographic test. With a biome map, BC 0.8.0 makes those follow the Deep North pixels of your map instead. This is new in 0.8.0 and has not yet been checked in play.
- **Leaving a biome out is fine.** On Valheim 1.0 a biome map that omitted a biome (for example no Mistlands) made world creation hang forever on the progress bar. BC 0.8.0 fixes that. Locations that need the missing biome are skipped and reported in the log (BC logs *"The biome map has no Mistlands..."*, and Valheim reports *"Failed to place all ..."*).
- **Layout matters.** Vanilla places many locations by distance from the world centre, so a sensible map keeps Meadows central and the harsh biomes outward. See also [Alt Biomes](#): the size and position of each biome region decides which alt biomes Valheim 1.0 can put there.
- The biome key image from the original repository (not shown on the site):

● Ocean	#0000FF
● Meadows	#00FF00
● Black Forest	#007F00
● Swamp	#7F7F00
● Mountains	#FFFFFF
● Plains	#FFFF00
● Mistlands	#7F7F7F
● Deep North	#00FFFF
● Ash Lands	#FF0000

New in BC 0.8.1:

- **Deep North weather at sea.** The game decides whether the weather should be Deep North weather by testing the camera's height where it should test the north-south position. On maps with Deep North across the middle, Deep North weather therefore showed up at sea in the wrong places. On Better Continents worlds with a biome map, Deep North weather at sea now follows the map, as Ashlands weather already does.
- **Alt biomes.** A separate alt-biome map, `altbiomemap.png`, plants Valheim 1.0's alt biomes on the regions you paint, without changing anything about the biome map. See [Planting alt biomes with colours](#).
- **Palette file.** `BetterContinents.gpl`, a palette for GIMP and Krita, holds the biome map colours in the table above and the default alt-biome colours. It comes in the release package and in the source repository's `palettes/` folder. See [Painting colour maps](#).
- **In-game edits.** When you change the biome map in game (for example with `bc b fn` or `bc reload bm`), Better Continents 0.8.1 also rebuilds the game's biome grid, so terrain biomes and alt biomes follow the new map at once. See [The cache file](#).
- **Locations that accept several biomes.** For such a location, Valheim 1.0 picks which of its biomes to search, and the pick goes wrong in three ways: it returns Black Forest for Plains, tests the Meadows flag for Ocean, and never picks the last matching biome. On a Better Continents world, when the pick is not one of the location's biomes or is absent from the map, one of its biomes that the map has is searched instead. A usable pick is kept, so complete maps place locations as before.

Biome precision

New in BC 0.10: Biome precision (`[03 BetterContinents.Biomemap]`, console `bc b p`) sets how closely the ground, grass, vegetation and spawn points follow your biome map inside each 64 m terrain zone. 0 is vanilla: a zone reads the biome map at its four corners only, so biome borders follow the 64 m zone grid and a small patch can fall between corners and vanish from the ground. A value N splits the zone into $(N + 1) \times (N + 1)$ cells. It never changes terrain height, and it never changes how locations or alt biomes are placed. The default is 0, and the config and the console accept 0 to 31. **On a new world (version 12) it goes up to 31**, which is 32×32 cells of 2 m; an older world (settings version 11) stops at 5, and reads a larger value as 5.

Biome precision	Cells per zone	One cell is about
0 (vanilla)	1×1 , the four corners	64 m
1	2×2	32 m
2	3×3	21 m

Biome precision	Cells per zone	One cell is about
3	4 × 4	16 m
4	5 × 5	13 m
5	6 × 6	11 m
7	8 × 8	8 m
15	16 × 16	4 m
31	32 × 32	2 m

A zone samples $(N + 2) \times (N + 2)$ points each time it is built, 1,089 at 31 against the four corners of vanilla, so a high value costs more work whenever a piece of ground is built: raise it step by step. [bc info](#) prints the cell size. See also [Export and Import](#).

Expand World Data


New in BC 0.10: Better Continents works with the Expand World Data mod. Since BC 0.9.3 a biome map's legend accepts the names that mod gives the biomes it adds (the names in its [expand_biomes](#) yaml) as well as the game's, and the world export writes them back. When Expand World Data is installed, a **new world** (settings version 12) also gets these:

- **Its altitude rules apply over your heightmap.** Expand World Data can change a biome's or a territory's altitude (a multiplier and a delta), the water depth, the height limits and the lava dip. On a new world these rules apply over the heights of your heightmap and roughmap, as they do over the game's own terrain. On an older world they showed only where the roughmap is 1. So a heightmap's heights are the world's heights only where no altitude rule applies; leave a biome's altitude settings at their defaults in Expand World Data if you want the heightmap exactly.
- **Its lava biomes are hot where the biome map puts them.** When the biome map decides what counts as Ashlands (a world with a biome map and no heat map, or a Heatmap Scale of 0), a biome that Expand World Data marks as a lava biome counts too: lava burns there, as it does in the Ashlands. Before, only the Ashlands pixels of a biome map were hot.
- **A terrain map can name its grounds.** A line of [terrainmap.txt](#) can name an Expand World Data biome for a colour's ground; see [Terrain map](#).
- **Biome precision keeps its territories' ground colours.** With Biome precision above 0, the ground colour that an Expand World Data territory sets is no longer replaced by the precision grid's colour. The terrain map still wins where it has a colour.
- **The world saves the names of the biomes it added.** Expand World Data numbers its biomes in the order of its yaml, and a world stores its biome map by those numbers, so putting the yaml in another order used to swap biomes. A new world saves the names of the added biomes its map holds, and the map follows the names: a biome that Expand World Data numbers differently now is read under its new number, and one it no longer has reads as *None* (the default generation decides there) until it has the biome again. The stored map and names are kept as they were, so nothing is lost when the yaml is put back. Install Expand World Data wherever the world is played, with the same yaml.


Biomemap Creation Hints

- Setup the biome colors as swatches, or a stored palette, for easy access.
- Place your heightmap on a background layer, then set your biome layers to 50% transparent.
- Use a separate layer for each biome, then you can reorder the layers if needed, and even apply layer edge effects.
- For each biome layer, fill it with the biome color entirely, then add a layer mask and paint into that, NOT the color part. This allows direct use of threshold onto the layer mask without having to convert it back and forth between color and black/white.
- Generate masks for the biomes based on height by using "Threshold". You can create a general land mask, and a mountains mask quite easily using this method. It can work for a basic Swamps mask as well.
- Improve the look of your Swamp mask by applying the water mask to it to exclude all water areas from the biome. This looks cleaner on the map and should reduce the number of enemy spawning in the water.
- If you have created a biome mask and want to grow or shrink its edges you can bake it into black and white, blur it, and then use Threshold again.
- Improve the look of the biome edges by using the smudge tool to roughen them up. After this you can reapply threshold to make the edges crisp again.


Examples



aus-biomemap.png



biomemap.png




middle-earth-biomemap.png

Console

Command: `bc b fn`

Updated for Valheim 1.0 / BC 0.8.0: Was `bc param b fn`. The animation was recorded with the old syntax. The `b` group also has `bc b p`, *Biome precision*, which is disabled in BC 0.8.0: the config calls it "Not working!" and BC logs a note to that effect.

New in BC 0.9.0: Biome precision works again. From 0 (vanilla: a 64 m terrain zone reads the biome map only at its four corners) to 5 (a corner every 11 m), it sets how closely ground texture, grass, vegetation and spawn points follow your biome map inside the zone; it never changes terrain height, and it never changes how locations or alt biomes are placed (those keep vanilla's four-corner, 12 m rules). Checked offline against the mod's own test suite, including a byte-identical comparison with vanilla's terrain builder at every precision level; not yet seen rendered in a running game. See [Export and Import](#).



5.5 Terrain map

By default, the ground texture is determined by the biome. The terrain map can be used to override this.

Color	Value	Texture
	#0000FF	Ocean
	#00FF00	Meadows
	#007F00	Black Forest
	#7F7F00	Swamp
	#FFFFFF	Mountains
	#FFFF00	Plains
	#7F7F7F	Mistlands
	#00FFFF	Deep North
	#FF0000	Ash Lands
	#000000	Default

Use 32 bit RGBA PNG for the terrainmap.

Updated for Valheim 1.0 / BC 0.8.0: The setting is **Terrainmap** file in the config section **03 BetterContinents.Biomemap**. The Project Directory file name is **terrainmap.png**, and the console command is **bc terrain fn**. The legend file **terrainmap.txt** is written next to the image with the defaults above if it is missing. Unlike the biome map, terrain map colours are matched exactly: a colour that is not in the legend is used as a raw ground colour.

New in BC 0.10: On a **new world**, a line of **terrainmap.txt** can name an Expand World Data biome for the ground, for example **DeadWastes: FF8000**: pixels of that colour get the ground colour that Expand World Data gives that biome, and the log says *Terrain map legend: DeadWastes is Expand World Data's biome, its ground colour* Before 0.10 such a name was not understood: it was read as a colour that does not parse, and the ground came out as Meadows' with a warning. Vanilla names, colours (even a name that reads as a colour) and names Expand World Data does not know are read as

written. The world keeps the ground colour, not the name, so its clients and anyone without Expand World Data read a plain colour. See [Biome map](#).

Color mapping

Previously shown colors are based on the default terrainmap.txt file.

Color mapping is used because alpha channel is difficult to use with some image editors.

Here are the actual internal colors used by the game. For example if you want to try different values.

Biome	Color
Default	#808080FF
Ocean	#00000000
Meadows	#00000000
Black Forest	#0000FF00
Swamp	#FF000000
Mountains	#00FF0000
Plains	#000000FF
Mistlands	#0000FFFF
Deep North	#00FF0000
Ash Lands	#FF0000FF

5.6 Heatmap

The Ashlands biome uses heat feature to make the water deal damage to ships and players.

By default, the boiling area matches the default generation of Ashlands biome. If you want to have boiling water somewhere else then you need to use the heat map.

Heat has intensity that affects how much damage is dealt to ships and how fast the player starts burning.

By default, the intensity increases when moving deeper into the Ashlands. Most effects cap after 300 meters when the intensity reaches 1. When partially standing on water, the effect caps after 3000 meters when the intensity reaches 10.

The heat map uses 10x scaling, so the max value of white color means 10 intensity.

Use 16 bit grayscale PNG for the heatmap.

Updated for Valheim 1.0 / BC 0.8.0:

- **Heat decides what counts as Ashlands.** With a heat map loaded, BC answers the game's "is this Ashlands?" question with *heat* > 0, literally. The heat map must therefore be **exactly 0** (pure black) everywhere on land that is not Ashlands. Any stray non-zero pixel silently turns that ground into Ashlands.
- **A sea ramp is fine.** Heat that extends into the water around the Ashlands, rising towards the coast, is what burns boats on the approach, just as in vanilla. Bound the heat geometrically around your Ashlands rather than tracing the biome edge.
- **No heat map?** If the world has a biome map but no heat map (or a Heatmap Scale of 0), BC takes "is this Ashlands?" from the biome map's Ashlands pixels instead. This is the fallback added in 0.7.28 so that lava still works.

- The file setting is **Heatmap File** in the config section **06 BetterContinents.Maps**. The Project Directory file name is **heatmap.png**, and the console command is **bc heatmap fn**.

Heat scale SETTING

Heat map scaling. Default is 10.

Updated for Valheim 1.0 / BC 0.8.0: The config name is **Heatmap Scale** (range 0 to 100) and the console command is **bc heatmap sc**. The config description adds: *Multiplies the heatmap color value. Most heat effects cap at 1 value.* A scale of 0 disables the heat map.

5.7 Paint map

The paint color is applied on top of the ground texture. This is used for player placed modifications like paving and cultivation.

However Mistlands and Ashlands also use this system for the alternative moss ground and lava.

To make editing easier, the default moss and lava generation is used when the color is fully opaque.

Different paints can be mixed but the ratios are not intuitive.

Paint	Color
Grass	#000000FF
Dirt	#FF0000FF
Cultivated	#00FF00FF
Paved	#0000FFFF
Moss	Depends on the alpha value
Lava	When alpha > 99
Patches	#00BF00FF
Grass Dark	#996600FF
Paved Moss	#000080FF
Paved Dirt	#FF0080FF
Paved Dark	#00FF80FF
...	Experiment

Note: Players can't modify the alpha channel, so using it on other biomes affects their terrain editing.

Moss and lava

Alpha channel can be difficult to use with some image editors. There are two ways around this:

- Use the **mossmap.png** and **lavamap.png** files for these features.
 - This is recommended if you don't have use for other paints.
- Use the **paintmap.txt** file to map opaque colors to the alpha channel.

Following rules apply:

- If the moss map exists and the biome is Mistlands, alpha value comes from the moss map.
- If the lava map exists and the biome is Ashlands, alpha value comes from the lava map.
- If the paint color is fully opaque, alpha value comes from the default generation.

4. Otherwise alpha value comes from the paint color.

Use 32 bit RGBA PNG for the paintmap.

Updated for Valheim 1.0 / BC 0.8.0: The setting is `Paintmap File` in the config section `06 BetterContinents.Maps`. The Project Directory file name is `paintmap.png`, and the console command is `bc paint fn`. The legend file `paintmap.txt` next to the image starts empty. Each line maps an image colour to a paint value as `PAINT: IMAGE`: the internal paint colour first, then the colour used in your image, each written as hex or as `r,g,b[,a]`. For example, `0000FFFF: 808080` would turn mid-grey pixels in the image into paved ground. Image colours not listed are used as they are.

5.8 Lava map

The lava map is an alternative way for defining where lava can appear. The other way is using alpha channel in the [paint map](#).

The lava map only affects the Ashlands biome. This means you don't need to worry about affecting other biomes.

Lava appears when the greyness is above 60% of the maximum value (99 of FF).

Use 16 bit grayscale PNG for the lavamap.

Updated for Valheim 1.0 / BC 0.8.0: The setting is `Lavamap File` in the config section `06 BetterContinents.Maps`. The Project Directory file name is `lavamap.png`, and the console command is `bc lava fn`.

5.9 Moss map

The moss map is an alternative way for defining where moss can appear. The other way is using alpha channel in the [paint map](#).

The moss map only affects the Mistlands biome. This means you don't need to worry about affecting other biomes.

Use 16 bit grayscale PNG for the mossmap.

Updated for Valheim 1.0 / BC 0.8.0: The setting is `Mossmap File` in the config section `06 BetterContinents.Maps`. The Project Directory file name is `mossmap.png` (0.7.31 fixed the old misspelt default `mossmap.png`), and the console command is `bc moss fn`.

5.10 Forest

Forest Scale

SETTING

Scales forested/cleared area size.

Default **0.5**
Range **0** to **1**

Updated for Valheim 1.0 / BC 0.8.0: In the BC 0.8.0 config, Forest Scale is declared with **default 1** and **range 0 to 10**. In BC 0.8.0 to 0.9.x the console command **bc fo sc** still showed default 0.5 and range 0 to 1; since 0.10 it shows the config's default and range. BC turns the value into a scale through a curve on which **0.5 is vanilla size**. Worked out from the source:


Forest Scale	Forest and clearing size
0	1/3 of vanilla
0.25	about 0.64 × vanilla
0.5	vanilla
0.75	about 1.8 × vanilla
1 (config default)	5 × vanilla
above about 1.15	broken: the scale reaches zero, then goes negative

So a world created from an untouched config gets forest and clearing patches five times larger than vanilla. Set 0.5 for vanilla-sized patches, and stay within 0 to 1.

Console

Command: **bc fo sc**

Updated for Valheim 1.0 / BC 0.8.0: Was **bc param fo sc**. The animation was recorded with the old syntax.



Frames 1, 31, 61 and 91 of 91 from the original animation `bc-param-fo-sc.gif` (33 s), left to right, top to bottom.

Forest Amount SETTING

Adjusts how much forest there is, relative to clearings.


Default **0.5**
Range **0** to **1**

Updated for Valheim 1.0 / BC 0.8.0: 0.5 is neutral (no change from the forest factor). Higher values give more forest.

Console

Command: **bc fo am**

Updated for Valheim 1.0 / BC 0.8.0: Was **bc param fo am**. The animation was recorded with the old syntax.



Frames 1, 35, 69 and 103 of 103 from the original animation `bc-param-fo-am.gif` (34 s), left to right, top to bottom.

Forest Factor Overrides All Trees SETTING


Trees in all biomes will be affected by forest factor (both procedural and from forestmap).

Default false

Console

Command: **bc fo ffo**

Updated for Valheim 1.0 / BC 0.8.0: Was **bc param fo ffo**. The value is **true** or **false**, and the world must be reloaded for a change to take effect. The animation was recorded with the old syntax.



Frames 1, 15, 30 and 44 of 44 from the original animation bc-param-fo-ffo.gif (14 s), left to right, top to bottom.

The forestmap controls the spawning of trees. By default this will only affect the Meadows and Plains trees (as in vanilla). You can also set "Forest Factor Overrides All Trees" to have forest factor (whether from vanilla procedural generation or the forestmap) control tree spawning in *all* biomes. i.e. You can have clearings in the Mistlands, the Swamps and even the Dark Forest! The minimap is also updated to show forest coverage on all biomes when this flag is active.

Updated for Valheim 1.0 / BC 0.8.0:


- **Minimap:** the last sentence no longer applies. In Valheim 1.0 the minimap's forest overlay is drawn by the game itself, and only for Meadows, Plains and Black Forest. Swamp, Mountain and Deep North get no overlay, and Mistlands uses its own mist shading. The game reads Better Continents' forest values for this, so the overlay follows your trees honestly. Older BC versions forced a forest overlay onto other biomes, which on Valheim 1.0 made Swamp, Mountain, Plains and Mistlands all draw as Black Forest. BC 0.8.0 removed that.
- **Which trees:** in the 0.8.0 source, this flag makes the forest factor control these vegetation prefabs: FirTree, FirTree_small, FirTree_small_dead, FirTree_oldLog, Pinetree_01, SwampTree1, SwampTree2, SwampTree2_log, SwampTree2_darkland, HugeRoot1, and the spider webs vertical_web, horizontal_web and tunnel_web.

Use 8 bit grayscale PNG of medium resolution for the forestmap. Image uses black as "no forest" zone and white as "forest" zone.

Console

Command: `bc fo fn`

Updated for Valheim 1.0 / BC 0.8.0: Was `bc param fo fn`. The animation was recorded with the old syntax.



Forestmap Multiply SETTING

How strongly to scale the vanilla forest factor by the forestmap.


Default **1**

Range **0** to **1**

Console

Command: **bc fo mu**

Updated for Valheim 1.0 / BC 0.8.0: Was **bc param fo mu**. The animation was recorded with the old syntax.



Forestmap Add SETTING


How strongly to add the forestmap directly to the vanilla forest factor.

Default **1**
Range **0** to **1**

Console

Command: `bc fo add`

Updated for Valheim 1.0 / BC 0.8.0: Was `bc param fo ad`. The subcommand is now `add`. The animation was recorded with the old syntax.



Frames 1, 23, 46 and 68 of 68 from the original animation `bc-param-fo-ad.gif` (26 s), left to right, top to bottom.

Recommended forest map settings

Updated for Valheim 1.0 / BC 0.8.0: This section is new in this edition. BC maps vanilla's forest factor to a 0-to-1 "forestness" (0 bare, 1 dense), combines it with the forest map value `fmap` as `Lerp(normalised, normalised × fmap, Multiply) + fmap × Add`, and maps the result back:

- With the defaults (Multiply 1, Add 1) this is `fmap × (normalised + 1)`, which saturates quickly and gives little control.
- With **Forestmap Multiply = 0** and **Forestmap Add = 1** it is `normalised + fmap`. A **higher forest map value then means more trees**, predictably.
- Leave **Forest Amount at 0.5**, which is neutral.

Don't hold densities down to protect the minimap: the overlay only exists in Meadows, Plains and Black Forest (see above).

5.11 Location map

The location map allows you to control where locations are placed when the world is created. The Location color chart below shows the various types of location that are supported, including all the start location, bosses, trader, and dungeons.

Updated for Valheim 1.0 / BC 0.8.0: The site never displayed the chart this sentence refers to. It is [images/spawnmap-ref.png](#) in the original repository, from the days when the location map was called the spawn map, and it is shown here:

Group	Quantity	Name	Color	Group	Quantity	Name	Color	Group	Quantity	Name	Color
Spawn	1	StartTemple	#FF0000	House	20	WoodHouse13	#6D9EEB	Shipwreck	25	ShipWreck03	#FCE5CD
Boss	3	Eikthymir	#FF9900	House	20	WoodHouse2	#6D9EEB	Shipwreck	25	ShipWreck04	#FCE5CD
Boss	4	GDKing	#00FF00	House	20	WoodHouse3	#6D9EEB	Spawn	200	GoblinCamp2	#BF9000
Boss	4	GoblinKing	#FFFF00	House	20	WoodHouse4	#6D9EEB	Spawner	200	DrakeNest01	#FFD966
Boss	5	Bonemass	#00FFFF	House	20	WoodHouse5	#6D9EEB	Spawner	200	FireHole	#F1C232
Boss	3	Dragonqueen	#4A86E8	House	20	WoodHouse6	#6D9EEB	Spawner	300	Greydwarf_camp1	#D9EAD3
Trader	10	Vendor_BlackForest	#0000FF	House	20	WoodHouse7	#6D9EEB	StoneCircle	25	StoneCircle	#A2C4C9
Abandonedcabin	33	AbandonedLogCabin02	#E6B8AF	House	20	WoodHouse8	#6D9EEB	Stonehenge	5	StoneHenge1	#F9CB9C
Abandonedcabin	33	AbandonedLogCabin03	#E6B8AF	House	20	WoodHouse9	#6D9EEB	Stonehenge	5	StoneHenge2	#F9CB9C
Abandonedcabin	50	AbandonedLogCabin04	#E6B8AF	House	200	StoneHouse3	#76A5AF	Stonehenge	5	StoneHenge3	#F9CB9C
Cave	250	TrollCave02	#C9DAF8	House	200	StoneHouse4	#76A5AF	Stonehenge	5	StoneHenge4	#F9CB9C
Crypt	200	Crypt2	#FFF2CC	Meteorite	500	Meteorite	#93C47D	Stonehenge	20	StoneHenge5	#F9CB9C
Crypt	200	Crypt3	#FFF2CC	Mountainruin	50	StoneTowerRuins04	#A61C00	Stonehenge	20	StoneHenge6	#F9CB9C
Crypt	200	Crypt4	#FFF2CC	Mountainruin	50	StoneTowerRuins05	#A61C00	Stonetower ruins	80	StoneTowerRuins03	#F6B26B
Crypt	400	SunkenCrypt4	#45818E	Ruin	50	SwampRuin1	#134F5C	Stonetower ruins	80	StoneTowerRuins07	#F6B26B
Dolmen	50	Dolmen03	#FFE599	Ruin	50	SwampRuin2	#134F5C	Stonetower ruins	80	StoneTowerRuins08	#F6B26B
Dolmen	100	Dolmen01	#FFE599	Ruin	200	Ruin1	#274E13	Stonetower ruins	80	StoneTowerRuins09	#F6B26B
Dolmen	100	Dolmen02	#FFE599	Ruin	200	Ruin2	#274E13	Stonetower ruins	80	StoneTowerRuins10	#F6B26B
Goblintower	50	Ruin3	#DD7E6B	Runestones	50	DrakeLorestone	#85200C	Swamphut	25	SwampHut5	#E69138
Goblintower	50	StoneTower1	#CC4125	Runestones	50	Runestone_Boars	#5B0F00	Swamphut	50	SwampHut1	#E69138
Goblintower	50	StoneTower3	#CC4125	Runestones	50	Runestone_Draugr	#4FCCCC	Swamphut	50	SwampHut2	#E69138
Grave	100	MountainGrave01	#6A844F	Runestones	50	Runestone_Greydwarfs	#EA9999	Swamphut	50	SwampHut3	#E69138
Grave	200	Grave1	#7F6060	Runestones	100	Runestone_Meadows	#E06666	Swamphut	50	SwampHut4	#E69138
GuckTree	700	InfestedTree01	#B6D7A8	Runestones	100	Runestone_Mountains	#CC0000	Waymarker	50	Waymarker01	#A4C2F4
House	20	WoodHouse1	#6D9EEB	Runestones	100	Runestone_Plains	#990000	Waymarker	50	Waymarker02	#A4C2F4
House	20	WoodHouse10	#6D9EEB	Runestones	100	Runestone_Swamps	#660000	Well	25	MountainWell1	#38761D
House	20	WoodHouse11	#6D9EEB	Ship	100	ShipSetting01	#D0E0E3	Well	25	SwampWell1	#0C343D
House	20	WoodHouse12	#6D9EEB	Shipwreck	25	ShipWreck01	#FCE5CD	woodvillage	10	WoodFarm1	#B45F06
				Shipwreck	25	ShipWreck02	#FCE5CD	woodvillage	15	WoodVillage1	#783F04

What BC actually uses is the legend file `locationmap.txt` next to your image, which BC writes with its defaults if it is missing. Its colours agree with the chart except for two entries, so take those colours from the file, not the chart:

Location	Chart	Default locationmap.txt
Greydwarf_camp1	#D9EAD3	217, 228, 211 = #D9E4D3
Waymarker01, Waymarker02	#A4C2F4	164, 195, 244 = #A4C3F4

The default file also lists two locations that the chart lacks: `Mistlands_DvergrBossEntrance1: 153,0,255` (the Queen's entrance) and `Hildir_camp: 255,105,180`. Each line is `LocationName: r,g,b` (hex also works), and the name is the game's location prefab name. You can add any other location, including Valheim 1.0 locations the defaults predate. Several names may share a colour, in which case each painted area picks one of them at random.

Image requirements

- 24 bit RGB png
- At least 329x329 to match in-game zones
 - Larger image can be used for more detail
- Use black background
- Colors must match exactly the locationmap.txt file

Behaviour

- All positions will be filled, even if that exceeds what the game usually places.
- The actual position is chosen from all adjacent pixels of same color.
- If you want multiple same locations next to each other, use a different color or make sure there is at least one pixel of black between them.
- After using the map, the game will continue with the default placement system. This can be disabled with the "Skip default locations" setting.

Updated for Valheim 1.0 / BC 0.8.0:

- The setting is `Skip Default Locations` (config section `01 BetterContinents.Global`, console `bc g skipdefaultlocations`). It is saved with the world. When it is on, every default location except the start temple is skipped, including the extra locations that Valheim 1.0's `alt biomes` would add.
- The start temple is placed by the location map if you paint one, or at the `Start Position` if that is overridden.
- **Checking the result:** `bc locs` prints how many of each location were placed and warns if any of `StartTemple`, `Eikthyrnir`, `GDKing`, `Bonemass`, `Dragonqueen`, `GoblinKing`, `Vendor_BlackForest` or `Mistlands_DvergrBossEntrance1` is missing. `bc bosses` pins those on the map. `bc show <prefix>` pins every location whose name starts with the prefix, and `bc hide <prefix>` removes those pins again. Careful: `bc hide` with no prefix removes *every* pin on the map, your own included.
- **Legacy name:** before 0.7.30 this map was the "spawnmap". BC 0.8.0 to 0.9.x took a `Spawnmap File` that was set while `Locationmap File` was empty for an old config: at launch it moved the path to `Locationmap File` (replacing "spawnmap" with "locationmap" in it), and when the world was created it renamed a `spawnmap.png` beside it to `locationmap.png`. Since BC 0.10 it does neither: `Spawnmap File` is only the creature spawn map (see `Spawn map`).

New in BC 0.10: On a **new world** a location lands **exactly on its pixel**, where the height and biome maps put that pixel (pixel i of a map of N pixels is at $i / (N - 1)$ across the map, so a 10,501 px map over 21,000 m has its pixels 2 m apart, the same grid as its heights). A pin of several pixels lands on the pixel nearest its middle, and where several locations share a colour they are dealt out the same way every time, so the same maps give the same world. An older world (settings version 11) still places a pin as 0.9 did: at the corner of a pixel picked at random from its area, up to a pixel south-west of where the other maps put it. The **maps of a world export** are the exception: an export writes each location's pixel for that corner reading, so a world built from an export reads its pins where the export wrote them.

The start position override is placed **before** the pins on a new world, so a pin in its zone cannot take it (see `Start Position`). On every world the log says when a pin's zone already holds another location, because the game keeps one location per zone.

Creation Hints

- Bring the spawn color table into your paint tool as a separate layer, or tabbed image, for easy access. Use the eye dropper on it to quickly select a spawn color.
- Draw spawn areas using a pencil tool NOT brush, as you want a hard edge and no color variation. Use a size that can be seen easily without having to zoom in. Slight randomization of the spawn location won't matter (see the example images).
- Place your heightmap/biome map background layers so you can easily see where you are placing spawns.
- Use a separate layer for each spawn type (bosses, markers, buildings etc.), then you can easily change the type of all of them in one go.

Console

Command: `bc 1 fn`

Updated for Valheim 1.0 / BC 0.8.0: Was `bc param s fn`; the location map group is now `1`.

5.12 Spawn map

The spawn map allows you to control where creatures spawn in the world. You can enable or disable spawns for different areas using specific colors.

Image requirements

- 24 bit RGB PNG
- 329x329 resolution to match in-game zones
 - Larger images won't give any benefit
- Use black background for default spawns
- Use white color to disable all spawns
- Other colors must match exactly the spawnmap.txt file

Behavior

- Spawns are enabled by setting the biome requirement to any biome.
 - Other requirements are currently not affected.
- Spawns are disabled by setting the biome requirement to no biome.
- `none`: disables all spawns
- `name`: enables a specific creature
- `-name`: disables a specific creature

Updated for Valheim 1.0 / BC 0.8.0: As implemented in the 0.8.0 source (the same code as 0.7.31), the entries in a `spawnmap.txt` line mean:

- `none`: disables every spawn in the area, except the creatures named on the same line.
- `+name`: **enables** the creature everywhere in the area, whatever its biome (the biome requirement is set to "any biome"; its other requirements still apply).

- **-name**: disables the creature.
- **name** with no prefix: only exempts the creature from **none** on the same line, so it keeps its normal spawning rules. On its own, without **none**, a bare name changes nothing.
- ***** wildcards are supported: **Troll***, ***_Elite**, ***camp***, **Goblin*Shaman**. Names are matched case-insensitively against prefab names.

Each line is **RRGGBB: entries** (or **r,g,b: entries**). Do not put **#** in front of the colour: a line starting with **#** is a comment. Pure white is always "none". Colours must match exactly, and an unknown colour is logged once and treated like black. The map is sampled at each zone's spawn system, so it works per 64 m zone. Event (raid) spawns are not affected.

Examples

```
# Red color is set to enable Wolves and Skeletons to spawn in that area
FF0000: Wolf, Skeleton

# Blue color is set to disable all spawns but enable Wolves and Skeletons
0000FF: none, Wolf, Skeleton

# Green color is set to disable Wolves and Skeletons
00FF00: -Wolf, -Skeleton
```

Updated for Valheim 1.0 / BC 0.8.0: Following the rules above, the first two examples do not do what their comments say in BC 0.8.0. Corrected versions:

```
# Red: also let Wolves and Skeletons spawn here, whatever the biome
FF0000: +Wolf, +Skeleton

# Blue: disable all spawns except Wolves and Skeletons, which keep their normal rules
0000FF: none, Wolf, Skeleton

# Blue variant: disable all other spawns and let Wolves and Skeletons spawn here in any biome
0000FF: none, +Wolf, +Skeleton

# Green: disable Wolves and Skeletons (unchanged)
00FF00: -Wolf, -Skeleton
```

Updated for Valheim 1.0 / BC 0.8.0: Setting the file. The config setting is **Spawnmap File** (section **06 BetterContinents.Maps**), the Project Directory file name is **spawnmap.png**, and the console command is **bc spawn fn**. Because "spawnmap" used to be the location map's name, BC 0.8.0 to 0.9.x treated **Spawnmap File** as an old location map path **whenever Locationmap File was empty**: at launch it moved the path over to **Locationmap File**, and the image later got renamed to **locationmap.png** (see **Location map**). A creature spawn map then needed the **Project Directory** or a **Locationmap File** as well.

New in BC 0.10: That is gone. **Spawnmap File** is the creature spawn map: it is not moved into **Locationmap File**, and a **spawnmap.png** beside a missing **locationmap.png** is not renamed.

Console

Command: **bc spawn fn**

Updated for Valheim 1.0 / BC 0.8.0: Was **bc param sm fn**; the group is now **spawn**.

5.13 Vegetation map

The vegetation map allows you to control where vegetation (trees, bushes, rocks, and other objects) appears in the world. You can enable or disable vegetation for different areas using specific colors.

Image requirements

- 24 bit RGB PNG
- At least 329x329 resolution to match in-game zones
 - Larger image can be used for more detail when disabling vegetation
- Use black background for default spawns
- Use white color to disable all spawns
- Other colors must match exactly the spawnmap.txt file

Updated for Valheim 1.0 / BC 0.8.0: For the vegetation map the legend file is `vegetationmap.txt`. Every colour-keyed map reads a legend named after its own image. The config setting is `Vegetationmap File` (section `06 BetterContinents.Maps`), the Project Directory file name is `vegetationmap.png`, and the console command is `bc vegetation fn`.

Behavior

- Vegetation are enabled by setting the biome requirement to any biome.
 - Other requirements are currently not affected.
 - This affects the whole 64m x 64m zone.
- Vegetation are disabled by "clear area" system that is more precise.
- `none`: disables all vegetation
- `name`: enables a specific vegetation object
- `-name`: disables a specific vegetation object

Updated for Valheim 1.0 / BC 0.8.0: The line syntax and prefixes are the same as the `spawn map`'s: `none` disables everything except the names on the same line, `+name` enables a vegetation prefab in any biome (for the whole zone), `-name` disables it (precisely, per placement point), a bare `name` only exempts it from `none`, and `*` wildcards work. Pure white means `none`, and a line starting with `#` is a comment.

Examples

```
# Red color enables only Beech trees and Rocks
FF0000: none, Beech1, Rock4_forest

# Blue color disables all vegetation but enables Pine trees
0000FF: none, FirTree

# Green color disables all vegetation starting with "Rock"
00FF00: -Rock*
```

Updated for Valheim 1.0 / BC 0.8.0: In the first two examples the named prefabs are *kept*, not force-enabled: they still only grow where they normally would. Use **+Beech1** to let beeches grow in other biomes too. **FirTree** is the fir; the pine is **Pinetree_01**.

Console

Command: **bc vegetation fn**

Updated for Valheim 1.0 / BC 0.8.0: Was **bc param vm fn**; the group is now **vegetation**.

Doubled vegetation and bc_twins

New in BC 0.10: The game seeds each vegetation entry's random numbers with the world seed, the zone and the prefab's name. Two entries for one prefab therefore draw the same spots, and a zone that is filled a second time over its own objects draws every spot again: trees and rocks then stand in pairs, a copy within inches or a metre of each one. A **+name** entry on the vegetation map, wildcards included, can make two entries for one prefab meet.

The twin guard. In every Better Continents world, a plant is not placed within 1 m of the same kind of object already standing in its zone, or placed there by another vegetation entry in the same pass. It changes vegetation only, never terrain, and only in zones generated from now on: a zone that is already generated keeps what it has. An entry never blocks its own placements, so the game's densities and groups stay as they are for every prefab with one entry, except beside an object of that prefab that already stands in its zone (one of a location placed just before, or of an earlier fill). Where two entries place the same prefab (a **+name** entry on the vegetation map, an alt biome's added vegetation), a second plant within 1 m of the first is dropped, so a zone generated from now on can hold slightly fewer plants than in 0.9.4. A zone filled twice no longer doubles its trees.

bc_twins finds and removes the twins a world already has. It is not a cheat command and any player can count with it. Removal runs where the world is: in single player, on a host, or on a dedicated server with **bc_twins server ...** (admins only; the answer comes back to the admin's console and the server's log). **bc twins** is the same command in the host's **bc tree**.

Command	What it does
bc_twins	Counts the twins by prefab and zone: exact ones (two copies on one spot, the mark of a zone filled twice) and near ones (the same prefab within 1 m, but apart). A client counts only the area around it; bc_twins server counts the whole world.
bc_twins <radius>	The same, with a radius from 0.1 to 5 m.
bc_twins remove [radius]	Shows what a cleanup would delete, and deletes nothing: exact twins only, or near ones too when a radius is given.
bc_twins remove confirm [radius]	Deletes the extra copies, 1000 a frame. The copy nearest the ground stays. Nothing a player built is ever deleted, and crops that players grow are removed only when two stand on exactly one spot.
bc_twins server ...	The same on a dedicated server.
bc_twins help	The usage.

Back up the world before **remove confirm**: it cannot be undone. The world saves as usual afterwards (**save** saves at once).

6 Settings

Settings are separated into two parts:

- **The Config Settings**

This contains settings that are not specific to any particular world.

Some are applied always to any active world (debug settings), and some are baked into the world when it is created (the terrain and spawning settings).

- **The World Settings**

These are the settings mentioned above, that are 'baked' into the world when it is created. Once baked, they can only be changed using the Console Commands, mentioned below.

The World Settings do not usually map directly to the values in the Config Settings, instead they are calculated from them.

Example:

In the Config Settings the 'Sea Level Adjustment' is specified as a 0 to 1 value, defaulting to 0.5, whereas the actual value generated in the World Settings is an absolute one from -0.25 to +0.25, which is then multiplied by 200 in the height generation algorithm to give a final value in meters of -50 m to +50 m.

So 0 Sea Level Adjustment in the Config Settings translates to -50 m change in Sea Level in game. You don't need to worry too much about this, just use the Console Commands below for tweaking these values, and you can immediately see what it looks like in game.

Updated for Valheim 1.0 / BC 0.8.0:

- **The example's numbers have changed.** In BC 0.8.0 the world value is `Lerp(1, -1, SeaLevel)`, from +1 at 0 to -1 at 1 and 0 at the default 0.5, so the full range is ± 200 m. A config value of 0 raises the land by 200 m (the sea level drops 200 m), and every 0.05 moves the water by 20 m. On new worlds it only has an effect when the world has a heightmap or [height layers](#). See [Global](#).
- **When the config is read.** Better Continents bakes the config values into a world when the world is created. In BC 0.8.0 the file was read once, when the game launched, so an edit on disk needed a relaunch; since BC 0.9.0 it is read again whenever it changes, so an edit counts for the next world you create (see [Export and Import](#)). The Configuration Manager (below) changes the running values directly.
- **Choosing the config when creating a world.** The world-creation panel has a preset dropdown next to the seed. It must be set to **From Config** for the config settings to be baked into the new world. It defaults to *Disabled*, which creates a vanilla world. It also lists the built-in presets (Continents, Pangaea, Swirls, Vanillaish) and any presets you saved with `bc savepreset`, stored in `<save folder>/BetterContinents/presets/`. The dropdown choice itself is remembered in the config as the hidden `SelectedPreset` value.

New in BC 0.10: The four built-in presets are old settings-version 7 presets, so a world made from one is a version 11 world, as in 0.9.4 ([Which version is my world?](#)).

BepInEx Configuration Manager

Config Settings can be accessed via the in game BepInEx Configuration Manager (see the [Setup Guide](#) for installation instructions).

It is opened by pressing F1, after which you can see sections for each BepInEx mod you have installed. Just click the sections to expand them, then change the settings.

Note: There is no "save" or "apply" button, the settings are saved automatically.

BepInEx Config File

You can also access the Config Settings in the config file itself. This is in the **BepInEx\config** directory in your Valheim installation directory. After running the game once with Better Continents installed the config file will be generated.

Updated for Valheim 1.0 / BC 0.8.0: The file is **BepInEx/config/BetterContinents.cfg**. With a mod manager, look in the profile's **BepInEx/config** folder instead of the game folder. BC 0.8.0 wrote these sections (later versions add keys and sections, listed completely in the *New in BC 0.10* box below):

Section	Settings
00 BetterContinents.Debug	Enabled, Debug Mode, Debug Reset Command, Override version, Directory
01 BetterContinents.Global	Skip Default Locations, Continent Size, World Size, Edge Size, Fix Water Color, Sea Level Adjustment, Ocean Channels, Ashlands Gap, Deep North Gap, Rivers, Map Edge Drop-off, Mountains Allowed At Center
02 BetterContinents.Heightmap	Heightmap File, Heightmap Amount, Heightmap Blend, Heightmap Add, Heightmap Mask, Heightmap Override All, Heightmap Alpha, Roughmap File, Roughmap Blend
03 BetterContinents.Biomemap	Biomemap File, Biome precision, Terrainmap file
04 BetterContinents.Forest	Forest Scale, Forest Amount, Forest Factor Overrides All Trees, Forestmap File, Forestmap Multiply, Forestmap Add
05 BetterContinents.StartPosition	Override Start Position, Start Position X, Start Position Y
06 BetterContinents.Maps	Locationmap File, Spawnmap File, Vegetationmap File, Paintmap File, Lavamap File, Mossmap File, Heatmap File, Heatmap Scale
07 BetterContinents.Misc	NexusID, SelectedPreset (both hidden from the Configuration Manager)

Numbers use a dot as the decimal separator.

New in BC 0.8.1: A new section, **08 BetterContinents.AltBiomes**, holds the alt-biome settings for new worlds: **Altbiomemap File, Mode, Grid, Fixed Seed, Chance Multiplier, Amount Multiplier, Region Size Scale, Distance Scale, Min Sector Thickness, Mean Sector Height, Fix Neighbour Check** and **Overrides**. See [Planting alt biomes with colours](#).

New in BC 0.9.0: **07 BetterContinents.Misc** also holds **Settings Transfer Rate (Vanilla, KB256, KB384, KB512, KB768, MB1, MB1_5, MB3, Unlimited)**: how fast a host or dedicated server sends a joining player their Better Continents settings and image maps. Only the sending machine's value counts. A new section, **09 BetterContinents.Export**, holds the export HUD's settings. Both are described in [Export and Import](#).

New in BC 0.10: The complete list of the sections and keys of `BetterContinents.cfg` as 0.10 writes them, in file order. Two keys are gone (**Fix Water Color** and **Ocean Channels**, in **01**), and **07** has gained **Compact Maps**, **Map Memory** and a hidden **Config Version**.

Section	Keys
00 <code>BetterContinents.Debug</code>	Enabled, Debug Mode, Debug Reset Command, Override version, Directory
01 <code>BetterContinents.Global</code>	Skip Default Locations, Continent Size, World Size, Edge Size, Sea Level Adjustment, Ashlands Gap, Deep North Gap, Rivers, Map Edge Drop-off, Mountains Allowed At Center
02 <code>BetterContinents.Heightmap</code>	Heightmap File, Heightmap Amount, Heightmap Blend, Heightmap Add, Heightmap Mask, Heightmap Override All, Heightmap Alpha, Roughmap File, Roughmap Blend
03 <code>BetterContinents.Biomemap</code>	Biomemap File, Biome precision, Terrainmap file
04 <code>BetterContinents.Forest</code>	Forest Scale, Forest Amount, Forest Factor Overrides All Trees, Forestmap File, Forestmap Multiply, Forestmap Add
05 <code>BetterContinents.StartPosition</code>	Override Start Position, Start Position X, Start Position Y
06 <code>BetterContinents.Maps</code>	Locationmap File, Spawnmap File, Vegetationmap File, Paintmap File, Lavamap File, Mossmap File, Heatmap File, Heatmap Scale
07 <code>BetterContinents.Misc</code>	NexusID, SelectedPreset, Settings Transfer Rate, Compact Maps, Map Memory, Config Version (NexusID, SelectedPreset and Config Version are hidden from the Configuration Manager)
08 <code>BetterContinents.AltBiomes</code>	Altbiomemap File, Mode, Grid, Fixed Seed, Chance Multiplier, Amount Multiplier, Region Size Scale, Distance Scale, Min Sector Thickness, Mean Sector Height, Fix Neighbour Check, Overrides
09 <code>BetterContinents.Export</code>	Hud, Allow Export, Hud Hotkey, Window Hotkey, Default Size, Default Heightmap Amount, Default Sea Level

- **Compact Maps** (**07**, default `false`, **experimental**) and **Map Memory** (**07**, default `512`, from 64 to 65536 megabytes) are described in [Export and Import](#).
- **Default Heightmap Amount** (**09**) is `1`, Better Continents' default everywhere. A `BetterContinents.cfg` that still holds the default of 0.9.0 to 0.9.4, `2`, is set to `1` once, and the log says so. The hidden **Config Version** records that this has been done, so a `2` that you choose afterwards stays.
- **Biome precision** accepts 0 to 31 in the config. A new world (version 12) uses it up to 31; an older world (settings version 11) uses it up to 5. **Start Position X** and **Y** accept $-1,000,000$ to $1,000,000$ metres. See [Biome map](#) and [Start Position](#).
- **Debug Reset Command** is empty by default: Better Continents regenerates the zones itself, and a console command written there runs instead. A `BetterContinents.cfg` that still holds the 0.9 default, `zones_reset start`, is set to empty once, and the log says so; the hidden **Config Version** records it. See [Debug](#) and [Zone regeneration](#).
- **Spawnmap File** is the creature spawn map. It is no longer moved into **Locationmap File** at startup, and a `spawnmap.png` beside a missing `locationmap.png` is no longer renamed. See [Spawn map](#).
- A line in an `export.cfg` for a setting that belongs to the machine, not to a world (**Settings Transfer Rate**, **Map Memory**, the **09** section), is ignored.

Console Commands

When you are loaded into a world that was created with Better Continents enabled, you can use an extensive set of console commands to modify the World Settings.

Open the Console with F1 (this mod enables it always), and then enter `bc` to get help on the basic commands. See the specific settings in this documentation (they are organised by group) for examples and documentation for each command.

Updated for Valheim 1.0 / BC 0.8.0:

- **The console opens with F5** (F1 is the Configuration Manager). Better Continents still enables the console.
- **`bc` is a cheat command**, and it is registered for the machine that hosts the world only (single player, or the host). Enable cheats with `devcommands` first; *Debug Mode* does this for you when you spawn. Valheim 1.0 also asks you to run `confirmcheats` before the first cheat command, which permanently marks the character as having used cheats, so use a test character. With the [Server Devcommands](#) mod installed, any player who has `devcommands` on can run `bc` on their own machine, but a change made there changes only that player's own copy of the settings and their own view of the ground, never the world or the other players, and the zone regeneration refuses (*it runs on the machine that runs the world*). Make `bc` changes on the host or in single player. `bc info` on a joined player's machine shows the settings the server sent.
- **The syntax is `bc <group> <setting> [value]`**. There is no `param` level any more, so the old `bc param g sl 0.5` is now `bc g sl 0.5`. Leave the value off to print the current value, or write `help` instead to see the range and description. On/off settings take `true` or `false`; the old `0/1` form is not accepted.
- **Every change** regenerates the terrain and the map, and resets the world's already-generated zones so that they generate again with the new settings. In 0.8.0 to 0.9.x that meant running the *Debug Reset Command*, Upgrade World's `zones_reset start` by default. Since 0.10 Better Continents resets the zones itself, apart from those around something a player built or worked, a tombstone, another player or you inside a dungeon, and a command written in *Debug Reset Command* still runs instead. Zones that are not reset keep their old locations and vegetation, but the ground of every zone follows the new settings. See [Debug](#).
- **Changes are saved** into the world's settings the next time the world saves.

New in BC 0.8.1: A change to the maps or settings in game now also rebuilds the world's biome grid, which in Valheim 1.0 decides terrain biomes as well as alt biomes, before the zones are regenerated. With 0.8.0 the grid kept following the old map until the world was loaded again. See [The cache file](#).

Console command reference

Updated for Valheim 1.0 / BC 0.8.0: This section is new in this edition. It lists the complete `bc` command tree (what 0.8.1, 0.9.0 and 0.10 added is marked).

Command	What it does
<code>bc</code>	Lists the commands
<code>bc info</code>	Prints the world's settings (the same output BC writes to the log)
<code>bc reload <map></code>	Re-reads an image map from disk: <code>hm</code> , <code>rm</code> , <code>fm</code> , <code>bm</code> , <code>terrain</code> , <code>lm</code> , <code>fom</code> , <code>paint</code> , <code>lava</code> , <code>moss</code> , <code>vegetation</code> , <code>heat</code> , <code>spawn</code> or <code>all</code> (only maps the world uses are offered)
<code>bc locs</code>	Counts placed locations and warns about missing key locations

Command	What it does
<code>bc bosses</code>	Pins the bosses, start temple, trader and the Queen's entrance on the map
<code>bc show [prefix ...]</code>	Pins every location whose name starts with a prefix (all locations if none is given)
<code>bc hide [prefix ...]</code>	Removes those pins. With no prefix it removes every pin on the map, your own included
<code>bc clouds</code>	Toggles the clouds on the large map
<code>bc mapds [0-3]</code>	Minimap downscaling power for faster regeneration (default 2)
<code>bc reset</code>	Redraws the minimap (revealing all of it), rebuilds the alt-biome grid, then rebuilds the loaded terrain and regenerates the zones, as a change does (most changes do all of this automatically)
<code>bc scr [size]</code>	Saves the map as a PNG (default 2048 px) in <code><save folder>/BetterContinents/<world name>/</code>
<code>bc savepreset [name]</code>	Saves the world's settings as a preset with a map thumbnail
<code>bc g ...</code>	Global: <code>cs, sl, r, ag, ng, me, mc, worldsize, edgesize, skipdefaultlocations</code>
<code>bc h ...</code>	Heightmap: <code>fn, am, bl, ad, ma, ov, alpha</code>
<code>bc r ...</code>	Roughmap: <code>fn, bl</code>
<code>bc b ...</code>	Biome map: <code>fn, p</code>
<code>bc terrain fn</code>	Terrain map file
<code>bc l fn</code>	Location map file
<code>bc paint fn, bc lava fn, bc moss fn</code>	Paint, lava and moss map files
<code>bc vegetation fn, bc spawn fn</code>	Vegetation and spawn map files
<code>bc heat ...</code>	Heat map: <code>fn, sc</code>
<code>bc fo ...</code>	Forest: <code>sc, am, ffo, fn, mu, add</code>
<code>bc st ...</code>	Start position: <code>os, x, y</code>
<code>bc hl ...</code>	Height layers
<code>bc ab ...</code>	New in BC 0.8.1: alt biomes: the alt-biome map, the mode, the grid, the random-placement controls and the reports. <code>bc reload ab</code> re-reads the alt-biome map. <code>bc ab help</code> lists the group.
<code>bc_altbiomes ...</code>	New in BC 0.8.1: a separate command for every player, on a client or on a host: the region you stand in, the alt-biome names and colours, and whether this machine's alt biomes agree with the server's. See Reports and commands .
<code>bc export ..., bc import ...</code>	New in BC 0.9.0: the world export and import, as <code>bc_export</code> and <code>bc_import</code> (below): <code>bc export run [options], status</code> and <code>cancel</code> ; <code>bc import run [what] [config], list</code> and <code>status</code> . See Export and Import .
<code>bc cache ..., bc twins ...</code>	New in BC 0.10: the same as <code>bc_cache</code> and <code>bc_twins</code> (below), inside the <code>bc</code> tree.
<code>bc regen</code>	New in BC 0.10: regenerates the world's zones now, as a change does, or runs the command in Debug Reset Command instead. It does not rebuild the loaded terrain (nothing has changed; a change rebuilds it first), redraw the minimap or rebuild the alt-biome grid. See Debug .


The original repository also contains four recordings that no page of the site displayed. They were recorded with an older Better Continents, so the commands they show include some that no longer exist (`bc param`, `bc refresh`, `bc despawnall`, `bc resetall` and `bc regenloc`).

Typing `bc` for help (older version):



Frames 1, 33, 65 and 96 of 96 from the original animation bc-help.gif (20 s), left to right, top to bottom.

bc info:



Frames 1, 7, 13 and 19 of 19 from the original animation bc-info.gif (5 s), left to right, top to bottom.

bc clouds:



Frames 1, 12, 24 and 35 of 35 from the original animation bc-clouds.gif (7 s), left to right, top to bottom.

bc mapds:



Frames 1, 13, 25 and 36 of 36 from the original animation bc-maps .gif (38 s), left to right, top to bottom.

New in BC 0.10:

- **Help for every group.** `bc <group> help` lists a group: `bc h help`, `bc l help`, `bc heat help` and so on. Before 0.10 the group descriptions pointed to a `bc param <group> help` that never existed, and `help` first printed an error before it listed the group.
- **The console shows the config's defaults and ranges.** Every setting has one declaration, so its default, range and description are the same in the config, in the console and in an export. A few had drifted in the console before 0.10: Heightmap Override All, Forest Scale (default 1, range 0 to 10), Forestmap Add and Start Position X and Y.
- **Tools for every player.** `bc_export`, `bc_import`, `bc_cache`, `bc_altbioomes` and `bc_twins` are commands of their own, not `bc` subcommands and not cheats, and each has its own rule about who may use it. On a dedicated server they answer the admin who ran them (`bc_export server ...`, `bc_twins server ...`) as well as the server's log. `bc cache` and `bc twins` are in the host's `bc` tree too.
- `bc info` prints the world's settings version first (Version 11 or Version 12). It also says when a world's maps follow its World Size, shows the record of a heightmap made by a world export, and, when the world has a heightmap and Heightmap Alpha is on, says how Heightmap Alpha reads it.
- `bc_twins` finds and removes doubled vegetation; see [Vegetation map](#).

The in-game settings window

Updated for Valheim 1.0 / BC 0.8.0: This section is new in this edition and was read from the source code. With **Debug Mode** on, on the machine hosting the world, a *Better Continents* button appears at the top left while the menu (Esc) or the large map is open. Alt+F8 also toggles the window while one of them is open, and does nothing elsewhere. The button opens the *Better Continents World Settings* window, which shows the same command tree as the console, with toggles, drop-downs and text fields, plus previews of the [height layer](#) noise.

6.1 Global

These settings affect the entire map.

Updated for Valheim 1.0 / BC 0.8.0: What applies to new worlds. Worlds created with BC 0.8.0 use Better Continents' third-generation height function. It only takes over from vanilla's terrain when the world has a [heightmap](#) or at least one [height layer](#). Without either, the terrain is vanilla, and Continent Size, Sea Level Adjustment and Mountains Allowed At Center have no effect. The older height function, and with it Mountains Amount, Ocean Channels and the ridges, is only used by worlds whose settings are stored in the old save formats (1 to 6). All of these settings are in the config section `01 BetterContinents.Global`, except *Enabled*, which is in `00 BetterContinents.Debug`.

Enabled SETTING

Whether this mod is enabled. If this is `false` when you create a new world then no features of Better Continents will affect that world. It disables BC Debug mode on that world as well.

Default `true`

Updated for Valheim 1.0 / BC 0.8.0: It only matters when the world is created from the config, that is with the preset dropdown set to *From Config*.

Continent Size SETTING

Continent size.


Default `0.5`
Range `0` to `1`

Updated for Valheim 1.0 / BC 0.8.0: On worlds created with BC 0.8.0, Continent Size only changes the size of the [height layer](#) noise features. It does not scale a heightmap or vanilla terrain. BC turns the value into a scale of 3.0 (at 0), 1.0 (at 0.5) or 0.2 (at 1) and divides each layer's frequency by it. So, unlike on older worlds, **higher values make the noise features smaller**, and 0.5 leaves them unchanged. This was worked out from the source code.

Console

Command: `bc g cs`

Updated for Valheim 1.0 / BC 0.8.0: Was `bc param g cs`. The animation was recorded with the old syntax, on an old-style world.



Frames 1, 33, 65 and 97 of 97 from the original animation `bc-param-g-cs.gif` (32 s), left to right, top to bottom.

Mountains Amount SETTING

Mountains amount.


Default **0.5**
Range **0** to **1**

Updated for Valheim 1.0 / BC 0.8.0: Removed. BC 0.8.0 has no Mountains Amount in the config and no console command for it (`bc g ma` does not exist). Only worlds stored in the old save formats keep and use a mountains amount.

Console

Command: `bc param g ma`

Updated for Valheim 1.0 / BC 0.8.0: This command no longer exists. The animation shows an older version.



Frames 1, 17, 33 and 48 of 48 from the original animation `bc-param-g-ma.gif` (21 s), left to right, top to bottom.

Sea Level Adjustment SETTING

Modify sea level, which changes the land:sea ratio.


Default **0.5**
Range **0** to **1**

Updated for Valheim 1.0 / BC 0.8.0: In BC 0.8.0 the height offset is `Lerp(1, -1, SeaLevel)`, which is 0 at the default 0.5, so every 0.05 raises (above 0.5) or lowers (below 0.5) the water by 20 m relative to the land. With a heightmap at the default Heightmap Amount, the waterline sits at heightmap value $(2 \times \text{SeaLevel} - 0.7)$: 0.30 at the default, 0 at a Sea Level of 0.35 (no sea at all) and 1.0 at 0.85 (everything under water). For example, `bc g sl 0.55` raises the water by 20 m. On new worlds it has no effect without a heightmap or height layers. See [Heightmap](#).

Console

Command: `bc g sl`

Updated for Valheim 1.0 / BC 0.8.0: Was `bc param g sl`. The animation was recorded with the old syntax, on an old-style world with the old ± 50 m range.



Frames 1, 27, 54 and 80 of 80 from the original animation `bc-param-g-sl.gif` (35 s), left to right, top to bottom.

Ocean Channels SETTING

Whether ocean channels should be enabled or not (useful to disable when using height map for instance).

Default **true**

Updated for Valheim 1.0 / BC 0.8.0: In BC 0.8.0 to 0.9.x the setting was still in the config, but the height function used by new worlds has no ocean channels, so it had no effect on them, and there was no console command for it. It only affected worlds stored in the old save formats.

New in BC 0.10: The setting is gone from the config. A world that saved it keeps what it saved: the old save formats (1 to 6) still read it in their height formulas, and `bc info` prints it.

ConsoleCommand: `bc param g oc`

Updated for Valheim 1.0 / BC 0.8.0: This command no longer exists. The animation shows an older version.



Frames 1, 13, 25 and 37 of 37 from the original animation `bc-param-g-oc.gif` (16 s), left to right, top to bottom.

Rivers SETTING


Whether rivers should be enabled or not.

Default `true`

Updated for Valheim 1.0 / BC 0.8.0: With a heightmap and [Heightmap Override All](#) on (the default), vanilla's rivers never appear whatever this says: carve rivers and lakes into the heightmap.

ConsoleCommand: `bc g r`

Updated for Valheim 1.0 / BC 0.8.0: Was `bc param g r`. The value is `true` or `false`; the animation shows the old `0/1` form.



Frames 1, 19, 38 and 56 of 56 from the original animation bc-param-g-r.gif (19 s), left to right, top to bottom.

Map Edge Drop-off SETTING


Whether the map should drop off at the edges or not (consequences unknown!).

Default **true**

Console

Command: **bc g me**

Updated for Valheim 1.0 / BC 0.8.0: Was **bc param g me**. The value is **true** or **false**; the animation shows the old syntax.



Frames 1, 15, 29 and 43 of 43 from the original animation bc-param-g-me.gif (17 s), left to right, top to bottom.

New in BC 0.8.1: Land beyond 10,500 m. Valheim's biome grid ends at 10,500 m, and every grid point beyond it is ocean. With Map Edge Drop-off off, land can continue past 10,500 m, and it took the ocean's grid region for its terrain biome, vegetation and spawns. Better Continents 0.8.1 gives it a plain region of its real biome instead, without alt biomes. See [How Valheim assigns them](#).

New in BC 0.10: On a new world whose World Size or Edge Size is not the default, the biome grid reaches the world's edge, so this applies beyond the grid, past World Size + Edge Size. See [World Size](#).

Mountains Allowed At Center SETTING

Whether the map should allow mountains to occur at the map center (if you have default spawn then you should keep this unchecked).


Default **false**

Updated for Valheim 1.0 / BC 0.8.0: This applies to heightmaps too. While it is off, BC caps the terrain within about 600 m of the world centre at 46 m above the water (a height of 0.38 before the $\times 200$), and blends back to the full height by 1,000 m from the centre.

Console

Command: **bc g mc**

Updated for Valheim 1.0 / BC 0.8.0: Was **bc param g mc**. The value is **true** or **false**; the animation shows the old syntax.



Frames 1, 19, 37 and 54 of 54 from the original animation `bc-param-g-mc.gif` (19 s), left to right, top to bottom.

World Size SETTING

Updated for Valheim 1.0 / BC 0.8.0: This setting is new in this edition's coverage. It is the world radius in metres. Default **10000**. Console: **bc g worldsize**. It moves the edge-of-the-world mechanics: where ships are pushed back and players are killed, and the water and wind at the edge. On an older world (settings version 11) it does not stretch the image maps, which cover the square from $-10,500$ m to $+10,500$ m on each axis (the Expand World Size mod can change that).

New in BC 0.8.1: Expand World Size. When Better Continents runs together with the Expand World Size mod, a world with a radius under 10,500 m no longer crashes (EWS issue #26), and larger worlds now map alt-biome regions correctly, together with the terrain biomes that come from the same biome grid. On its own, Better Continents 0.8.1 can also stop that grid at a world edge inside 10,500

m; see the *Grid* setting under [Planting alt biomes with colours](#).

New in BC 0.10: A new world is made to its World Size. On a new world (version 12), World Size and Edge Size decide the size of the whole world, not only its edge:

- **The maps** (every image map) span the square from $-(\text{World Size} + \text{Edge Size})$ to $+(\text{World Size} + \text{Edge Size})$ on each axis. With the defaults that is the same 21,000 m as before, so the maps of a world of the default size span what they always did; World Size 20000 with Edge Size 500 gives maps 41,000 m across. The procedural noise of the [height layers](#) keeps the size of its features in metres: the world's size only sets the square over which its lowest and highest values are measured.
- **The alt-biome grid** covers the world, and the game places its **locations** at the grid's points, so they reach the whole world: they are searched for within World Size. See [Alt Biomes](#).
- **The game's own layout** follows World Size: its biome bands (the Swamp's limit included) where no biome map decides, the Ashlands and Deep North rings with their gaps and the Deep North's calm sea, and the area searched for lakes and stream sources. The **minimap** covers the whole world, out to World Size + Edge Size (its texture keeps its size, so its pixels grow). Terrain detail, the hills, rocks and noise, keeps its size.
- **The land** drops away over Edge Size past World Size, as before (see [Map Edge Drop-off](#)).
- The alt-biome **Grid** setting has no effect on such a world.

An older world (settings version 11) keeps its 21,000 m maps and vanilla's layout, and World Size only moves its edge. `bc info` prints the world's settings version first, and says when a world's maps follow World Size, and when the world is laid out to that size. The console accepts 0 to 1,000,000 m for World Size and for Edge Size, as it did before 0.10.

Limits. A bigger world builds a bigger alt-biome grid each time it loads, on the server and on every client as it joins, which takes longer and holds more memory (about 0.2 GB at a radius of 16,350 m). The practical maximum is **World Size + Edge Size of about 16,350 m**: Valheim files every object farther than about 16.35 km from the centre under one shared sector, so a world should stay inside it.

Expand World Size. With Expand World Size installed, it lays out the world, as before. Install it on every machine that plays the world, or on none, and do not add it to a world that Better Continents laid out. Its *World Stretch* setting magnifies Better Continents' maps, so that only their centre shows; the log carries a warning (on any Better Continents world, not only a new one), and World Stretch is best left at 1 on a Better Continents world.

Edge Size SETTING

Updated for Valheim 1.0 / BC 0.8.0: This setting is new in this edition's coverage. It is the width in metres of the band at the edge of the world, beyond the world radius. Default **500**. Console: `bc g edgesize`.

New in BC 0.10: On a new world the land drops away over the Edge Size, and the maps span World Size + Edge Size on each side of the centre (see [World Size](#)).

Ashlands Gap SETTING

Updated for Valheim 1.0 / BC 0.8.0: This setting is new in this edition's coverage. It controls whether vanilla's ocean gap around the Ashlands is kept ("usually custom maps don't need this"). Default `false`, which means BC removes the gap. Console: `bc g ag`.

Deep North Gap SETTING

Updated for Valheim 1.0 / BC 0.8.0: This setting is new in this edition's coverage. It controls whether vanilla's ocean gap around the Deep North is kept. Default `false` (removed). Console: `bc g ng`.

Skip Default Locations SETTING

Updated for Valheim 1.0 / BC 0.8.0: This setting was covered on the [Debug](#) page, and since 0.7.30 it lives in this section and is saved with the world. It skips the default location placement; the start temple and the location map's locations are still placed. Default `false`. Console: `bc g skipdefaultlocations`.

Fix Water Color SETTING

Updated for Valheim 1.0 / BC 0.8.0: This setting is new in this edition's coverage. Config description: *Whether to fix the water color*. Default `true`. Console: `bc g fixwatercolor`. In BC 0.8.0 to 0.9.x the value was stored with the world, but the code that used it was switched off, so it had no effect.

New in BC 0.10: The setting and its console command are gone: the config no longer has it and `bc g fixwatercolor` does not exist. A world that saved the value keeps it (`bc info` prints it). It has had no effect since BC 0.8.0.

6.2 Project

The project setting allows the use of standardized names for the image maps to enable automatically using them from a specified directory. This works only from the config during world generation. Once the world is generated the console commands can be used to change the filepath for each image map separately.

Directory SETTING

This directory will load automatically any existing map files matching the correct names, overriding specific files specified below.

Only png is supported using this method, however png is the recommended format in general as it supports both 16 bit grayscale, and 8 bit RGB, and these cover the requirements of all the image types.

If you specify a directory, the specific file path settings are all ignored, even if the project directory doesn't contain a file that would override them. i.e. You can *either* specify a Project Directory and follow these naming conventions, OR you must specify each file path separately using its associated setting (in the table below). You can't mix these methods.

Updated for Valheim 1.0 / BC 0.8.0: The setting is **Directory** in the config section **00 BetterContinents.Debug**. In the console, a map's **fn** command also resolves bare file names against this directory: for example **bc h fn heightmap** finds **heightmap.png** there.

New in BC 0.9.4: If the directory holds an **export.cfg**, it is the folder of a **world export**, and a new world created with **From Config** also takes the settings in that **export.cfg**, laid over **BetterContinents.cfg** the way an import lays them. Its settings win: to use a value of your own, such as another Heightmap Amount, edit **export.cfg** in the folder or delete it. **Directory** itself stays as **BetterContinents.cfg** has it, so a moved or copied export folder loads its maps from where it is now, and nothing is written to either file. The log (**BepInEx/LogOutput.log**) says *Directory ... holds a world export* and lists every setting that differs from your config. A directory without **export.cfg**, such as your own maps, works as before: every setting comes from **BetterContinents.cfg**. Before 0.9.4 an export folder loaded this way kept the config's default Heightmap Amount of 1, but the exports of 0.9.x store their heights for Amount 2, so the world came out almost all ocean.

New in BC 0.10: An export made by 0.10 stores its heights for Heightmap Amount 1 by default, as Better Continents does everywhere, and says so twice: in its **export.cfg** and inside **heightmap.png** itself (see **Heightmap**). A new world made from an export folder, with **From Config**, **bc_import** or an export's own preset, is a world of the newest settings version (12) when the export's maps span what its own World Size and Edge Size give, which every export of a version 12 world does, and every 0.9.x export of a world of the normal size. Otherwise it is a version 11 world, which gets none of the new-world changes: an export of a world resized under 0.9.x spans 21,000 m whatever its World Size said, and an export made under Expand World Size at another size spans that mod's size. Such an export is rebuilt as the world it was (one made under Expand World Size at another size only with Expand World Size installed at that size). A folder of maps you made yourself, with no **export.cfg**, makes a version 12 world, which reads the same files the 0.10 way: location pins exactly on their pixels, the start position placed before the pins, the heightmap's alpha blended when Heightmap Alpha is on, finer Biome precision, Expand World Data's rules, and maps that span World Size + Edge Size. To get the 0.9.4 result, set **Override version** to **11** before you create the world.

Filenames

File Name	Target Setting
heightmap.png	Heightmap File
roughmap.png	Roughmap File
flatmap.png	Flatmap File
biomemap.png	Biomemap File
forestmap.png	Forestmap File
spawnmap.png	Spawnmap File

Updated for Valheim 1.0 / BC 0.8.0: The complete list of file names BC 0.8.0 looks for in the directory:

File Name	Map
heightmap.png	Heightmap
roughmap.png	Roughmap
biomemap.png	Biome map
terrainmap.png	Terrain map

File Name	Map
heatmap.png	Heat map
paintmap.png	Paint map
lavamap.png	Lava map
mossmap.png	Moss map
forestmap.png	Forest map
locationmap.png	Location map (what older versions called the spawnmap)
spawnmap.png	Spawn map, the creature spawn map
vegetationmap.png	Vegetation map

flatmap.png is no longer loaded (see [Flatmap](#)). The colour legends ([biomemap.txt](#), [terrainmap.txt](#), [paintmap.txt](#), [locationmap.txt](#), [spawnmap.txt](#), [vegetationmap.txt](#)) are read from the same folder, and BC writes any that are missing.

New in BC 0.8.1: One more file name: [altbiomemap.png](#), the [alt-biome map](#), with its legend [altbiomemap.txt](#). When the directory is set, only a file of this name in it is used, as for every map.

6.3 Ridges

Ridges are an extra layer of procedural noise generation (i.e. not using an image, but calculated "randomly" instead) you can introduce into the height generation that have a "ridged" and/or "warped" appearance. This can give quite interesting and realistic topology, roughly emulating folding, or the collision of tectonic plates.

Updated for Valheim 1.0 / BC 0.8.0: The ridge settings are gone. BC 0.8.0 has no ridge settings in the config and no [ri](#) console group; the commands are commented out in the source. Only worlds whose settings are stored in the old save formats still use their stored ridge values. For new worlds, ridged and warped terrain comes from the [Height Layers](#): apply the *Ridges* noise preset to a layer (`bc hl <n> npreset ri`), and add a noise warp for the folded look. The original descriptions and recordings below are kept for reference.

Max Ridge Height SETTING


Max height of ridge features (set this to 0 to turn OFF ridges entirely).

Default [0.5](#)
Range [0](#) to [1](#)

Console

Command: `bc param ri mh`

Updated for Valheim 1.0 / BC 0.8.0: This command no longer exists.



Frames 1, 22, 44 and 65 of 65 from the original animation bc-param-ri-mh.gif (24 s), left to right, top to bottom.


Ridge Size SETTING

Size of ridge features.

Default 0.5
Range 0 to 1

Console
Command: bc param ri si

Updated for Valheim 1.0 / BC 0.8.0: This command no longer exists.



Frames 1, 32, 63 and 93 of 93 from the original animation bc-param-ri-si.gif (32 s), left to right, top to bottom.

Ridge Blend SETTING

Smoothness of ridges blending into base terrain.


Default **0.5**

Range **0** to **1**

Console

Command: `bc param ri bl`

Updated for Valheim 1.0 / BC 0.8.0: This command no longer exists.



Frames 1, 21, 41 and 60 of 60 from the original animation `bc-param-ri-bl.gif` (18 s), left to right, top to bottom.

Ridge Amount SETTING

How much ridges.


Default **0.5**

Range **0** to **1**

Console

Command: `bc param ri am`

Updated for Valheim 1.0 / BC 0.8.0: This command no longer exists.



Frames 1, 25, 49 and 72 of 72 from the original animation `bc-param-ri-am.gif` (22 s), left to right, top to bottom.

6.4 Height Layers

Updated for Valheim 1.0 / BC 0.8.0: This chapter is new in this edition. All of its text is edition text, worked out from the BC 0.8.0 source code. The original guide does not cover height layers. They replace the [Ridges](#) and the [Flatmap](#) on new worlds.

Height layers are Better Continents' procedural terrain for new worlds. A world can have any number of layers of [FastNoiseLite](#) noise. Each has its own noise type, fractal settings, optional domain warp, optional mask and a Photoshop-style blend mode, and they are applied in order on top of the heightmap. A world with neither a heightmap nor any height layer uses vanilla terrain.

The config has no entries for height layers. You build them in game with the `bc hl` commands or in the [settings window](#). They are saved with the world, and `bc savepreset <name>` saves them into a preset. Choosing that preset in the world-creation dropdown is how a new world gets them. The four built-in presets (Continents, Pangaea, Swirls, Vanillaish) are all three-layer stacks:

1. a base fBm layer (blend Normal);
2. an fBm detail layer with a noise warp and a warped mask;
3. a warped, non-fractal layer multiplied over the result (blend Multiply).

New in BC 0.10: The built-in presets are old settings-version 7 presets, so a world made from one is a version 11 world, as in 0.9.4 ([Which version is my world?](#)).

How layers combine

For every point, BC starts from the heightmap's value (`heightmapValue × Heightmap Amount` with the default heightmap settings), or from 0 when there is no heightmap. It then applies the layers in order:

```
layerValue = Blend(value, noise, blendMode)
value      = mask ? Lerp(value, layerValue, maskNoise) : layerValue
```

The result then goes through the usual `- 0.15 + SeaLevelAdjustment`, and the height in metres is that $\times 200$ (see [Heightmap](#)). Points to know:

- Each noise is normalised to the range 0–1 over the world, then passed through the layer's filters in this order: invert, smooth threshold, range, threshold, opacity.

- **A new layer's blend mode is Normal, which replaces everything below it**, including your heightmap, unless the layer is masked. To add detail on top of a heightmap instead of replacing it, choose another blend mode (for example *LinearDodge*, which adds, combined with a small *Range*), or give the layer a mask.
- Blend modes (*a* is the value so far, *b* is the layer): Normal (*b*), Darken (min), Multiply, ColorBurn, LinearBurn, Lighten (max), Screen, ColorDodge, LinearDodge ($a + b$), Overlay, HardLight, SoftLight, VividLight, LinearLight, PinLight, HardMix, Difference, Exclusion, Subtract ($a - b$), Divide.
- Masks, and mask presets, are available from the second layer (layer 1) on.
- Frequencies are in cycles per metre (the default 0.0005 is one cycle every 2 km), and are divided by the scale set by [Continent Size](#).
- Layer seeds are derived from the world seed.

Commands

Layers are numbered from 0. Every change regenerates the terrain, like any other **bc** change.

Command	What it does
<code>bc hl add</code>	Adds a layer at the end: OpenSimplex2 fBm, 7 octaves, frequency 0.0005, blend Normal
<code>bc hl <n> npreset def</code>	Resets the layer's noise to the default fBm noise
<code>bc hl <n> npreset ri</code>	Sets the layer's noise to the <i>Ridges</i> preset (ridged fractal)
<code>bc hl <n> n <setting> [value]</code>	The layer's noise settings (table below)
<code>bc hl <n> nw on true</code>	Adds a domain warp to the noise, whose settings are then under <code>bc hl <n> nw ... on false</code> removes it
<code>bc hl <n> mpreset def / 25%</code>	Layers 1 and up: sets a default mask with smooth-threshold values 0.6–0.75 (the command's description says "about 25 % coverage"). In the 0.8.0 source the preset does not switch the smooth threshold on, so follow it with <code>bc hl <n> must true</code>
<code>bc hl <n> mpreset ri</code>	As above, plus a mask warp for ridge-like shapes
<code>bc hl <n> m on true</code>	Layers 1 and up: enables a mask, whose settings are then under <code>bc hl <n> m ... on false</code> removes it
<code>bc hl <n> mw on true</code>	Layers with a mask: adds a warp to the mask (<code>bc hl <n> mw ...</code>)
<code>bc hl <n> delete</code>	Deletes the layer
<code>bc hl <n> down</code>	Swaps the layer with the next one (for layers between the first and the last)

Noise, warp and mask settings share these keys. Some only appear when they apply: the fractal keys when the fractal type is not None, **ps** for PingPong, the **c...** keys for Cellular noise, and **dt/da** for warps.

Key	Setting	Values
nt	Noise type	OpenSimplex2, OpenSimplex2S, Cellular, Perlin, ValueCubic, Value
fq	Frequency	default 0.0005
asp	Aspect ratio (scales y relative to x)	default 1
ft	Fractal type	None, FBm, Ridged, PingPong. For warps: None, DomainWarpIndependent, DomainWarpProgressive
fo	Fractal octaves	1 to 10
fl	Fractal lacunarity	0 to 10, default 2
fg	Fractal gain	0 to 2, default 0.5
ws	Fractal weighted strength	–2 to 2, default 0
ps	Ping-pong strength	0 to 10, default 2

Key	Setting	Values
cf	Cellular distance function	Euclidean, EuclideanSq, Manhattan, Hybrid
ct	Cellular return type	CellValue, Distance, Distance2, Distance2Add, Distance2Sub, Distance2Mul, Distance2Div
cj	Cellular jitter	0 to 2, default 1
dt	Domain warp type	OpenSimplex2, OpenSimplex2Reduced, BasicGrid
da	Domain warp amplitude (m)	0 to 20000. The warp presets use 4000
in	Invert	true / false
ust, sts, ste	Smooth threshold: on, start, end	start and end -1 to 1
ura, ras, rae	Range: on, start, end (rescales 0-1 to start-end)	-1 to 1
uth, th	Hard threshold: on, value	0 to 1
uop, op	Opacity: on, value	0 to 1. See the note below
blm	Blend mode	see above

Things to know in BC 0.8.0:

- **List settings need the settings window.** The console can only parse text, numbers and **true/false**, so typing a value for a setting that is picked from a list (**nt**, **ft**, **cf**, **ct**, **dt**, **blm**) fails with an error. Change those in the [settings window](#) (Debug Mode), which also shows a preview image of each layer and of the final result.
- **Opacity is miswired.** The **op** command reads and writes the layer's *Threshold* value instead of its opacity, so opacity cannot currently be set. Use *Range* to scale a layer down instead.

6.5 Start Position

Override Start Position SETTING

Whether to override the start position using the values provided (warning: will disable all validation of the position).

Default false

Start Position X SETTING

Start position override X value, in metres from the world's centre (vanilla's world reaches 10500 either way).

Default 0

Range -1000000 to 1000000

Start Position Y SETTING

Start position override Y value, in metres from the world's centre (vanilla's world reaches 10500 either way).

Default `0`

Range `-1000000` to `1000000`

Updated for Valheim 1.0 / BC 0.8.0: The values are world coordinates in metres. Y is the world's north-south axis (Valheim's z), with north positive. The settings are in the config section `05 BetterContinents.StartPosition`. In the console they are `bc st os (true/false)`, `bc st x` and `bc st y`. In BC 0.8.0 to 0.9.x the console help for `x` and `y` showed a range of 0 to 1 and the config allowed `-10,500` to `10,500`, though the values are used as metres. The start temple is registered at that position when the world's locations are generated, so the override only matters when the world is created.

New in BC 0.10: Both settings accept `-1,000,000` to `1,000,000` metres, in the config and in the console, so the start can be anywhere in a bigger world (see [World Size](#)). The console shows the same range and default as the config.

On a **new world** the start position override is placed **before** the location map's pins, so a pin in the same 64 m zone cannot take it: the game keeps one location per zone. An older world (settings version 11) places it after the pins, as it always did, and a pin in its zone wins. On every world the log now says when a zone is already taken: an error when the start position finds its zone taken (the game then places the start itself), a warning when a pin does.

6.6 Debug

Debug Mode SETTING

For editing a world's settings live with the `bc` commands: when you spawn it turns on cheat mode, and it gives you the settings window. It does not reveal the map. Leave it off for a world you play.

Updated for Valheim 1.0 / BC 0.8.0: Default `false`, in the config section `00 BetterContinents.Debug`. In the 0.8.0 source, Debug Mode takes effect on the machine that hosts a Better Continents world. When you spawn it switches on `devcommands`, it shows *Better Continents Debug Mode Enabled!* at the top left, and it adds a *Better Continents* button to the Esc menu and the large map, which opens the [settings window](#) (Alt+F8 does the same while the Esc menu or the large map is open, and does nothing elsewhere). It does not reveal the map when you respawn; the setting's older description, which said that it does, was wrong in 0.9.x as well. What reveals the whole map is a `bc` change that redraws the minimap, as most changes do: the redraw explores all of it.

New in BC 0.10: After each change made with the `bc` commands or in the settings window, Better Continents also regenerates the world's zones itself. That comes with the `bc` commands, not with Debug Mode: they need cheats on, which Debug Mode does for you when you spawn (typing `devcommands` does it too). See [Zone regeneration](#).

Skip Default Location Placement SETTING

Skips default location placement during world gen, the spawn temple and spawnmap items are still placed. This is particularly useful when vanilla spawn placement during world creation is likely to fail, and you don't want to wait for it.

Updated for Valheim 1.0 / BC 0.8.0: Since 0.7.30 this setting is called **Skip Default Locations**, lives in the config section **01 BetterContinents.Global** and is saved with the world. Its console command is **bc g skipdefaultlocations**. "Spawnmap items" means the **location map**'s locations. It also skips the locations that Valheim 1.0's **alt biomes** add.

Debug Reset Command SETTING

Updated for Valheim 1.0 / BC 0.8.0: This setting is new in this edition's coverage. It is a console command that BC runs after every world-setting change made with **bc** (and on **bc reset**). In BC 0.8.0 to 0.9.x the config described it as the *Upgrade World command to execute when reloading images* and its default was **zones_reset start**, Upgrade World's command, which resets already-generated zones so that they regenerate with the new settings; without Upgrade World installed the command did nothing.

New in BC 0.10: Debug Reset Command is empty by default, and an empty setting leaves the regeneration to Better Continents: see [Zone regeneration](#). A console command written there runs instead, after each change made with **bc** and on **bc regen**, and Better Continents then does not regenerate the zones itself. For example **zones_reset start**, the command of Upgrade World, resets the zones with that mod.

A **BetterContinents.cfg** that still holds the old default, **zones_reset start**, is set to empty once, when the game starts, and the log says: *BetterContinents.cfg: [00 BetterContinents.Debug] Debug Reset Command was "zones_reset start" (the default of Better Continents 0.9) and is now empty: Better Continents regenerates the zones itself. Write "zones_reset start" there again to run that console command instead.* The hidden **Config Version** in section **07 BetterContinents.Misc** records that this has been done, so a **zones_reset start** that you write afterwards stays. Any other command that was in the setting is left as it was.

Override version SETTING

Updated for Valheim 1.0 / BC 0.8.0: This setting is new in this edition's coverage. In BC 0.8.0 to 0.9.x its config description was *Override the save version*: it makes BC write its settings in an older save format. It is a developer option: leave it empty.

New in BC 0.10: The config description is now: *Empty (the default): every world is saved in its own settings version (one older than 11 as 11), and a new world gets the newest (12, made by 0.10). A number here saves every world in that version instead, and a new world made From Config gets it when it is 11 or more: 11 makes worlds as Better Continents 0.9 did. For testing only: a world saved in an older version than its own loses what its version added.*

- **A new world** made with **From Config** gets settings version 12 when this is empty, and version 12 carries the 0.10 behaviour of new worlds. A whole number of 11 or more makes a world of that version instead: **11** makes a version 11 world, which plays as a 0.9 world did (its maps span 21,000 m whatever its World Size says, and so on) and gets none of the new-world changes. Only the preset file that **bc_import** or an export builds ignores this setting (it is written in the version of its

own settings). A world made from any preset is saved by the ordinary creation save, which uses this setting when it is set, so it is saved in that version like every world (see the next point).

- **Every world** is saved in this version while it is set, and a host sends this version to joining players, so a world does not keep its version for good while this is set. **11** saves a version 12 world as version 11, which loses what 12 added from its next load; **12** stamps a version 11 world as 12 at its next save, so from the next load the zones generated follow the 0.10 rules, and seams are likely where they meet the old ones. A number below 11 writes the old fixed layout of that number and drops data. The setting is read at every save, so an edit counts for the next save of a loaded world. Leave it empty, on a server above all.
- **An import** with `bc_import ... config`, or an `export.cfg` pasted into `BetterContinents.cfg`, sets it back to empty, because every `export.cfg` lists it as empty.

Which version is my world? `bc info` prints **Version 11** or **Version 12** first. The four presets that ship with the mod (Continents, Pangaea, Swirls and Vanillaish) are old version 7 presets, so a world made from one is a version 11 world. To make a world as 0.9.4 would have made it, on purpose, set **Override version** to **11** before you create the world with **From Config**, and empty it again afterwards. Nothing converts an existing world from version 11 to 12: this setting can only stamp one at its next save, which is not recommended. The Better Continents README sets this out in full, with a table of what each version does, in its section *Upgrading from 0.9: existing worlds and new worlds*.

Zone regeneration

New in BC 0.10: The game fills a zone, a 64 m square of the world, with its trees, rocks, buildings and creature spawners once, when somebody first comes near, and then keeps what it made. A zone that is already generated therefore does not follow a change that you make with `bc` or in the settings window. Better Continents regenerates the world's zones itself, after every change made with `bc` (or in the settings window) and on `bc regen`.

- **Where it runs.** Wherever the `bc` commands run: on the machine that runs the world (single player or the host), in a world that uses Better Continents. They are cheat commands, so cheats must be on (`devcommands`, which Debug Mode turns on when you spawn); Debug Mode is not needed otherwise. A player who has joined someone else's world holds none of the world's objects. The `bc` command is registered for the machine that runs the world only, but with the Server Devcommands mod installed, any player who has `devcommands` on can run it on their own machine. A change made there changes only that player's own copy of the settings and their own view of the ground, never the world or the other players, and the zone regeneration refuses with *Zone regeneration: it runs on the machine that runs the world: in single player, or on the host. Make bc changes on the host or in single player.* A world without Better Continents is the game's own, and Better Continents never empties its zones: there the console says *Zone regeneration: this world does not use Better Continents*.
- **What is reset.** Every generated zone, except the zones within one zone of something that has to stay: a zone and the eight around it (the 3 × 3 block) are left alone when it holds
 - something a player built or planted (anything placed from the build menu or planted with the cultivator: buildings, chests, ships, portals, crops and saplings while they grow),
 - a tombstone,
 - ground work, ground that a player has changed with the hoe, the cultivator or the pickaxe (fields, paths, roads, levelled or dug ground), or
 - you, while you are inside a dungeon.

A player connected from another machine keeps the zones their game has loaded around them: their simulation distance, which is the 5×5 block around them with the game's default setting, and never less than the 3×3 block. Their game still has the settings it joined with (a change reaches only the machine that runs the world), so what was built there would not fit their ground. This is checked again as the work goes, so a player who moves keeps the zones around where they are now, and something you build while it runs keeps its zone from then on. The ground around your own character on the surface is regenerated like the rest, and nobody's dungeon is reset under them: inside a dungeon you keep the 3×3 block, or the widest block that a connected player keeps, if that is wider.

- **Locations stay whole.** A location can reach over the edge of its zone into the next (a village, a camp, a ruin). The zones that one location reaches into are kept or reset together, and so are those of any location that shares a zone with it: if any zone of such a group is within reach of something that stays, every generated zone of the group is kept. When a group is reset, the parts of its locations that stand in a zone nobody has generated yet are cleared with them, so resetting again does not leave a second copy standing.
- **What stays.** Players, what players built, tombstones and tamed animals are never removed, in a zone that is reset or not. Everything else in a reset zone is removed: the trees, rocks and buildings that the world made, creatures that are not tamed, and items lying on the ground. Crops are kept with their field: cultivated ground is ground work, so its zone stays. A tree that a player grew from a sapling has no maker once it has grown, so it counts as the world's and goes unless something nearby keeps its zone. A creature that a creature spawner made goes with its spawner, wherever it has walked to, unless it is tamed or stands in a zone that is left alone.
- **Afterwards.** Each reset zone generates again with the current settings (the world's own: a world of version 11 edited with **bc** keeps its 0.9.x rules), its locations included, when somebody comes near, and not before the zones around it that are being reset have been cleared too, so a location that reaches over a zone edge is built once, whole. A location stays on the spot that the world gave it when the world was created: it is built again there, on the ground as it is now. Zones that are not reset keep what they have, their ground apart (see *Kept zones and the ground*). Where a zone that stays meets a zone that was reset, Better Continents clears the height edits of the ground (hoe, pickaxe, levelling) along the shared edge and corner, on the side that stays, so that the two grounds meet instead of cracking or stepping; the paint of the ground stays. It does this for the zones that were actually reset, when the work is done and at every save, also after a run that was cut short.
- **Kept zones and the ground.** Zone regeneration keeps what players built and the zones within one zone of it, with their trees and rocks. The ground of every zone, kept ones included, is built from the world's settings, though, so after a change it follows the new settings. The edits that players made with the hoe, the cultivator or the pickaxe are stored as changes to the ground and ride on the new ground (along the edge a kept zone shares with a reset one they are cleared, as the bullet above says). A change that lowers the ground under a base leaves its pieces standing in the air, and the game breaks a piece that has lost its support a few seconds later (in a test of 0.10, a workbench and a floor left about 3 m up broke after about 8 seconds); a change that raises the ground buries them. Trees and rocks in kept zones float or sink the same way. So make big height changes before you build, or away from what you want to keep. **bc regen** on its own changes no ground.
- **How it runs.** The work is spread over frames, so the game keeps running, the zones nearest the players first (the rebuild of the loaded terrain that a change starts with is not part of it: it happens at once, see **bc regen** below). With other players connected it removes at most 100 objects a frame and about 6,000 a second, which leaves their connection its room. After a change it starts once the alt-biome grid has been rebuilt, if the change needs that. The console shows a line when

it starts, a progress line every tenth of the way and a line when it finishes (lines like the ones below), and the screen shows how far it has got. A zone is checked again when its turn comes: if it has gained a reason to stay since the start (a player has arrived, you built beside it), it is left alone, together with the rest of its location's zones, and with the zones around it when the reason stands in the zone itself. A zone that the work has begun on is always finished. A change made while it runs, or **bc regen** again, starts it over, and the zone it was in is finished first; the zones that the first run had emptied but not finished are reset by the new one, whatever has come near them since. If you leave the world, it stops and says so, and **bc regen** in the next session starts it again. If an error stops the work, the zones it had emptied and left waiting for their neighbours are finished, so they generate again when somebody comes near, and the zones it had not reached are as they were: **bc regen** resets them.

- **Saves.** A zone is never saved half emptied, and a location is never saved half cleared. If the world is saved while the work is going (an autosave, or logging out), the zone being emptied is finished first, a location that the work has begun on is cleared whole, and the zones it has emptied so far are saved as not generated, so they generate again when somebody comes near. The other zones it has not reached keep what they have.
- **Limits.** A tree grown from a sapling far from anything that keeps its zone counts as the world's. A zone that was already reset is not brought back when something is built beside it afterwards. A location whose home zone the game generates while the work is running (someone came near it) can end up half placed, or placed twice; **bc regen** again sets it right. On a very large world, beyond about 16 km from the centre, the game files every object under one shared sector, so the scan of the world's objects is slower there.

Zone regeneration: resetting 1,204 of 1,500 generated zones; 296 left alone (near something a player built or worked on, a tombstone, or a player; 40 of them to keep a location whole).

The first line gives the zones to reset out of all the generated ones, and how many are left alone (the numbers in these lines are only an example). The part after the semicolon appears only when a location keeps some of them.

Zone regeneration: 121 of 1,204 zones (10%), 8,531 objects removed.

A progress line like this comes every tenth of the way, only when 20 or more zones are to be reset. It counts the zones dealt with, reset or left alone.

Zone regeneration finished in 12.4 s: 1,204 zones reset, 85,321 objects removed. 3 objects stay (players, what players made, tombstones, tamed animals). A reset zone generates again with the new settings when somebody comes near.

The last line starts with the zones reset and the objects removed. The sentences after that appear only when they apply, in this order:

- *3 objects stay (players, what players made, tombstones, tamed animals).* for what is never removed in the zones that were reset,
- *3 zones were left alone after all: a player, or something a player made, was in or beside them before their turn.* for zones that gained a reason to stay before their turn,
- *2 more zones were left alone to keep a location whole.* for zones that were left alone because a zone of the same location was (*2 zones were left alone to keep a location whole.* when the sentence before it is absent),
- *The ground at the edge of 3 left-alone zones was adjusted to meet the reset zones. (1 left-alone zone for one)* for the ground mended at a border,
- *2 errors, see the log.* when objects could not be removed, and

- *A reset zone generates again with the new settings when somebody comes near.* when at least one zone was reset.

Other lines you may see:

- *Zone regeneration: no generated zone to reset (296 generated zones are left alone).* takes the place of the first line when every generated zone is left alone.
- *Zone regeneration stopped after 340 of 1,204 zones: the world closed.* takes the place of the last line's first sentence, and its closing sentence is missing, when you leave the world while the work is going.
- *Zone regeneration stopped by an error, see the log.* appears when an error ends the work. The log then says what became of the zones the work had emptied and left waiting for their neighbours: *Zone regeneration: 3 zones left waiting were finished, so they generate again with the new settings when somebody comes near. The zones it had not reached are as they were: 'bc regen' resets them. (1 zone left waiting was finished, so it generates again ... for one).*
- *Zone regeneration: load a world first., Zone regeneration: it runs on the machine that runs the world: in single player, or on the host.* and *Zone regeneration: this world does not use Better Continents.* appear when there is no world, this machine does not run it, or the world has no Better Continents.

New in BC 0.10: `bc regen` does what a change does to the zones, on demand: it regenerates the zones, and does nothing else. It does not rebuild the terrain that is loaded, because nothing has changed and the ground already matches the settings. A change made with the `bc` commands or in the settings window (any setting, `bc reset`, an alt-biome change, a map reload, Biome precision) rebuilds the loaded terrain once first (the distant terrain and the grass too, and a zone that is loading at that moment) and then regenerates the zones. That rebuild stalls the game for a second or two (1.6 s in a test), as the rebuild after a change did in 0.9.4; the regeneration itself is spread over frames. With a command in [Debug Reset Command](#), `bc regen` runs that command instead of regenerating the zones, and rebuilds no terrain then either. In a world without Better Continents it says *Zone regeneration: this world does not use Better Continents.* and rebuilds nothing. It takes no arguments, and `bc regen help` says what it does. It does not redraw the minimap or rebuild the alt-biome grid. `bc reset` does: it redraws the minimap (and reveals all of it), rebuilds the alt-biome grid and the loaded terrain, and then regenerates the zones, as a change does. Most changes run all of `bc reset` for you; a change to Biome precision, which changes only how a zone reads the biome map, and the `bc ab` commands, which rebuild as much of the alt-biome data as they affect, leave the minimap alone.

Debug Mode and the `bc` commands are for worlds you are building. A reset zone loses what the world had put in it, so back a world up before you use `bc` on one that matters.

7 Alt Biomes

Updated for Valheim 1.0 / BC 0.8.0: This chapter is new in this edition, and all of its text is edition text. The alt biome data was extracted from the game's own asset bundles (the list [AltBiomes_Erik](#)), and the assignment rules were read from the game code. The sizes in the tables were calculated for round regions on the game's 12 m grid.

New in BC 0.8.1: Better Continents 0.8.1 lets you plant alt biomes where you want them, gives world owners control over the game's random placement, and fixes bugs in the pipeline that decides them. See [Planting alt biomes with colours](#). Worlds that use none of the new features get the same regions and the same alt biomes as with 0.8.0.

What alt biomes are

Valheim 1.0 has **32 alt biomes**: named variants that the game layers onto whole regions of a biome, such as *Dark Meadows*, *Birch Meadows*, *Troll Black Forest*, *Bog Swamp*, *Wolf Mountain*, *Goblin Plains* or *Rockless Mistlands*. An alt biome can add or remove creature spawns, add or remove vegetation, add or remove locations, remove weather types, and raise the chance that creatures spawn at a higher level. (The game's alt biome format can also rename a region or force music or weather, but none of the 32 do.) Each region can carry several alt biomes at once, as long as they are not incompatible with each other.

Alt biomes are not painted anywhere. The game assigns them every time a world loads, from the world's shape and its seed. On a Better Continents world, "the world's shape" is your maps, so your biome map and heightmap decide which alt biomes can exist and where.

New in BC 0.8.1: You can now also paint them: an alt-biome map plants chosen alt biomes on chosen regions, and the game's random placement fills in the rest (or nothing, if you prefer). See [Planting alt biomes with colours](#).

Coverage by biome: Meadows and Black Forest each have 9 possible alt biomes (counting those shared with other biomes), Mistlands 7, Swamp 6, Plains 6, Mountain 4 and Deep North 1 (*Lantern*). Ashlands and Ocean have none.

How Valheim assigns them

1. **Sampling.** When a world loads, on the server and on every client separately, the game samples it on a **2048 × 2048 grid of points 12 m apart**, centred on the world centre. Every point records its biome and its height. Points more than 10,500 m from the centre count as Ocean. With Better Continents, the biome comes from your biome map and the height from your heightmap and height layers.
2. **Sectors.** Every **4-connected region of one biome** (neighbours left, right, up and down; diagonals do not count) becomes a *sector*. The exceptions are **Ashlands, Deep North and Ocean**, which are each a **single global sector** containing all of that biome's points, wherever they are.
3. **Measuring a sector.** A point is an *edge point* if one of its four neighbours belongs to a different sector. For every sector the game records:
 - **edge count**, the number of its edge points, which for a round region is about **0.47 × its radius in metres**;
 - **centre**, the mean position of its edge points, and the **distance from the world centre** to that point;
 - **height**, the midpoint between the lowest and the highest height found on its edge points.

4. **Rules.** A sector can receive an alt biome only if:

- its distance from the world centre is at least the alt biome's minimum distance;
- its edge count lies inside the alt biome's window (minimum inclusive, maximum exclusive);
- its height is at least 30 m, which is the water level (all 32 alt biomes use a window of 30 m to 10,000 m);
- it does not already carry an alt biome that is incompatible with this one, in either direction.

The game's format also supports required or forbidden neighbouring biomes and world X/Y limits, but none of the 32 use them.

5. **Order and chance.** The game walks the biomes in the order Meadows, Swamp, Mountain, Black Forest, Plains, Ashlands, Deep North, Ocean, Mistlands, and within each biome the alt biomes in list order (the # column below). For each alt biome it shuffles that biome's sectors, with a shuffle seeded from the world seed, the biome and the alt biome's name, and goes through them. While fewer than the **minimum** count have been placed, every sector that passes the rules gets the alt biome. After that, each passing sector gets it with the alt biome's **chance**, until the **maximum** count is reached. An alt biome listed for several biomes shares one count across all of them. Because incompatibility is checked against what a sector already carries, alt biomes earlier in the list win conflicts.
6. **Report.** When fewer than the minimum could be placed, the game logs *Loading: Placed X/min-max of 'Name' altbiome*. Search **Player.log** (or the BepInEx log) for that line to see which alt biomes your map could not host.

The assignment is deterministic: the same maps and seed always give the same result.

New in BC 0.10: The grid of a new world covers the world. On a new world (version 12) whose World Size or Edge Size is not the default (and without Expand World Size, which lays out its own), Better Continents lays the grid out to the world's size: its points are still 12 m apart, and there are as many as cover the world's radius with vanilla's margin (4000 × 4000 points for a radius of 20,500 m). Past 8192 points on a side, a radius over 42,000 m, the points grow instead, to keep the grid's memory in bounds. The grid, its regions and the locations that the game places at its points then reach the whole world, so the alt biomes can too. A bigger grid takes longer and more memory each time the world loads, on the server and on every client as it joins (about 0.2 GB at a radius of 16,350 m). An older world (settings version 11) keeps the 2048 × 2048 grid that reaches 10,500 m. See [Global](#).

New in BC 0.8.1: In Valheim 1.0 this grid is not only for alt biomes. Every terrain chunk takes the biomes at its corners from it, so it also decides the terrain biomes that vegetation, spawns and terrain colour follow. Three 0.8.1 fixes therefore matter beyond alt biomes:

- **In-game map edits** now reach the grid; see [The cache file](#) below.
- **Expand World Size.** When Better Continents runs with the Expand World Size mod, a world with a radius under 10,500 m no longer crashes (EWS issue #26), and larger worlds now map alt-biome regions correctly across the whole world, and with them the terrain biomes that come from the same grid.
- **Land beyond 10,500 m.** Past 10,500 m every grid point is ocean. On a Better Continents world with Map Edge Drop-off off, land continues there and took the ocean's region for its terrain biome, vegetation and spawns. It now gets a plain region of its real biome, without alt biomes.

The cache file

Valheim 1.0.7 and 1.0.12 cached the sampled points in `<save folder>/cache/<world name>_biomedatacache.bin` and reused them on later loads. **Since 1.0.15 the game no longer reads that file.** On every world load, on the server and on every client, it deletes the file and samples the grid again. The grid is therefore never stale across loads, and there is nothing to delete by hand.

New in BC 0.8.1: In-game map edits reach the grid. The game builds the grid each time a world loads (on the server, and on every client as it joins), but Better Continents' `bc` commands (`bc reload ...` and the other map and setting changes made with them) change maps and settings live. With 0.8.0 the alt-biome regions and the biomes of terrain chunks kept the grid from before the edit until the world was loaded again. Better Continents 0.8.1 rebuilds the grid, the regions and the placement whenever they change, and only then regenerates the zones. The same step also clears each terrain chunk's stored corner regions.

The 32 alt biomes

Placement rules, in list order. *Count* is the minimum and maximum number of sectors per world. *Edge count* is inclusive. *Incompatible with* lists both directions, because the game checks both. *≈ radius* is the radius of a round, smooth region with that edge count; a region with a ragged outline has more edge points than a round one of the same size.

#	Alt biome	Biomes	Min. distance (m)	Count	Chance	Edge count	≈ radius (m)	Incompatible with
0	Mushroom	Meadows, Black Forest	500	1-3	0.2	66-198	144-426	-
1	Lantern	all land biomes except Ashlands	500	3-5	0.2	66-198	144-426	-
2	Bones	Swamp, Plains, Mistlands	2000	1-3	0.2	66-198	144-426	Peaceful Meadows
3	Menhir	Meadows, Plains	750	1-3	0.2	33-198	74-426	Birch Meadows
4	Dark Meadows	Meadows	1900	2-5	0.5	66-298	144-638	Peaceful Meadows
5	Peaceful Meadows	Meadows	1000	1-2	0.2	99-298	214-638	Bones, Dark Meadows
6	Dandelion Meadows	Meadows	500	1-3	0.2	66-198	144-426	-
7	Raspberry Meadows	Meadows	500	1-3	0.2	66-198	144-426	-
8	Smalltree Meadows	Meadows	500	1-3	0.2	33-198	74-426	-
9	Birch Meadows	Meadows	500	1-3	0.2	66-198	144-426	Menhir
10	Troll Black Forest	Black Forest	750	1-3	0.2	66-198	144-426	-
11	Root Black Forest	Black Forest	2000	1-4	0.2	99-298	214-638	Rock Black Forest, Kalhygge Black Forest
12	Ruin Black Forest	Black Forest	500	1-5	0.2	33-198	74-426	-
13	Rock Black Forest	Black Forest	750	1-5	0.2	33-198	74-426	Root Black Forest, Pinetree Black Forest
14	Pinetree Black Forest	Black Forest	750	1-5	0.2	33-198	74-426	Rock Black Forest
15	Blueberry Black Forest	Black Forest	500	1-5	0.2	33-198	74-426	-
16	Hut Swamp	Swamp	1500	1-3	0.2	33-198	74-426	Bog Swamp
17	Bog Swamp	Swamp	1500	1-5	0.2	33-144	74-312	Hut Swamp
18	Bat Swamp	Swamp	2000	1-3	0.2	33-144	74-312	-
19	Abomination Swamp	Swamp	2000	1-3	0.2	66-144	144-312	-

#	Alt biome	Biomes	Min. distance (m)	Count	Chance	Edge count	≈ radius (m)	Incompatible with
20	Wolf Mountain	Mountain	2000	1-5	0.2	199-298	426-638	Drake Mountain, Fortress Mountain
21	Drake Mountain	Mountain	2000	1-3	0.2	199-298	426-638	Wolf Mountain, Fortress Mountain
22	Fortress Mountain	Mountain	2000	1-2	0.2	199-298	426-638	Wolf Mountain, Drake Mountain
23	Lox Plains	Plains	2000	0-1	0.2	99-298	214-638	Goblin Plains, Death Plains
24	Goblin Plains	Plains	2000	0-2	0.2	66-198	144-426	Lox Plains, Death Plains
25	Death Plains	Plains	1000	0-1	0.2	99-298	214-638	Lox Plains, Goblin Plains
26	Kalhygge Black Forest	Black Forest	500	1-2	0.2	20-79	47-174	Root Black Forest
27	Rockless Mistlands	Mistlands	2000	2-5	0.2	99-598	214-1275	-
28	Trees Mistlands	Mistlands	2000	1-5	0.2	59-298	129-638	-
29	Swords Mistlands	Mistlands	2000	1-3	0.2	59-198	129-426	-
30	Hare Mistlands	Mistlands	2000	1-3	0.2	59-198	129-426	-
31	BroodSwarm Mistlands	Mistlands	2000	1-3	0.2	59-198	129-426	-

What each one changes. Creatures, and added vegetation, are listed by prefab name. Removed vegetation is listed by the game's vegetation entry name, so where both lists mention the same prefab (as in *Rockless Mistlands*), the alt biome replaces vanilla's entry with its own at a different density. Numbers after an added location are its quantity. "Inactive entries" are present in the game data but cannot take effect.

#	Alt biome	What it changes
0	Mushroom	Adds vegetation Pickable_Mushroom
1	Lantern	Adds vegetation deepnorth_lantern_standing
2	Bones	Adds creatures Skeleton_Poison; adds vegetation LargeBone, LargeBone_half01, LargeBone_half02
3	Menhir	Adds creatures Skeleton, Skeleton_Mountains; adds vegetation Rock_7_meadows
4	Dark Meadows	Adds creatures Draugr; adds locations WoodVillage2 (15); removes locations WoodFarm1; removes weather Clear, LightRain; creature level-up chance x2. Inactive entries: Draugr_Elite (entry is for Swamp only)
5	Peaceful Meadows	Adds creatures Boar, Deer; removes creatures Greyling, Greydwarf, Skeleton, Draugr, Troll; adds vegetation FireFlies. Inactive entries: Deer_White (entry disabled)
6	Dandelion Meadows	Adds vegetation Pickable_Dandelion
7	Raspberry Meadows	Adds vegetation RaspberryBush
8	Smalltree Meadows	Adds creatures Neck; adds vegetation Beech_small1, Beech_small2, stubbe, Bush01, Beech1; removes vegetation entries beech1_meadows, birch1_meadows, birch2_meadows. Inactive entries: shrub_2 (entry disabled)
9	Birch Meadows	Adds creatures Deer; adds vegetation Birch1, Birch2, Beech1, Oak1; removes vegetation entries beech1_meadows
10	Troll Black Forest	Adds creatures Troll
11	Root Black Forest	Adds creatures TentaRoot_wild, Greydwarf_Elite; removes creatures Skeleton; adds vegetation Greydwarf_Root, Greydwarf_Surprise
12	Ruin Black Forest	Adds vegetation stone_wall_2x1_ruin, stone_wall_1x1_ruin, stone_wall_ruin, stone_wall_ruin_2, GhostSkull; adds locations StoneTowerRuins07_sunk (10), StoneTowerRuins08_sunk (10), StoneTowerRuins09_sunk (10), StoneTowerRuins10_sunk (10)

#	Alt biome	What it changes
13	Rock Black Forest	Adds vegetation rock4_forest, Rock_3, Rock_4, FirTree_small, stubbe, FirTree; removes vegetation entries firtree_many_blackforest, Pinetree_01_blackforest, firtree_blackforest; removes locations TrollCave02; creature level-up chance x2
14	Pinetree Black Forest	Adds vegetation Pinetree_01; removes vegetation entries firtree_blackforest, firtree_many_blackforest, firtree_small_blackforest; creature level-up chance x2
15	Blueberry Black Forest	Adds vegetation BlueberryBush
16	Hut Swamp	Adds vegetation SwampTree1, SwampTree2, wooden_path, wood_pole_log_4_worn; removes vegetation entries swamptree1, swamptree2; adds locations SwampHut1_1 (50), SwampHut2_1 (50), SwampHut3_1 (50). Inactive entries: Wraith (never spawns: no biome area)
17	Bog Swamp	Adds creatures Abomination; adds vegetation StatueEvil, SwampTree2_log, FirTree_small_dead, SwampTree1, SwampTree2; removes vegetation entries swamptree1, swamptree2; removes locations InfestedTree01
18	Bat Swamp	Adds creatures Bat_Swamp
19	Abomination Swamp	Adds creatures Abomination
20	Wolf Mountain	Adds creatures Wolf; removes creatures Skeleton, Hatchling; adds vegetation FirTree; removes vegetation entries rock1_mountain, rock2_mountain; creature level-up chance x2
21	Drake Mountain	Adds creatures Hatchling; removes creatures Wolf, Skeleton; adds vegetation rock3_mountain_1; removes vegetation entries firtree_mountain; creature level-up chance x2
22	Fortress Mountain	Adds creatures Skeleton_Mountains, StoneGolem; adds vegetation stone_wall_ruin, stone_wall_ruin_2, rock3_mountain_1; removes vegetation entries firtree_mountain; adds locations StoneTowerRuins05_leet (10); removes locations StoneTowerRuins05; creature level-up chance x3
23	Lox Plains	Adds creatures Lox; removes creatures Goblin; removes vegetation entries birch2_aut_heath; removes locations GoblinCamp2, StoneTower1, StoneTower3
24	Goblin Plains	Adds creatures Goblin; removes creatures Lox, Deathsquito; adds locations GoblinHut01 (30), GoblinHut02 (30), GoblinHut03 (20); creature level-up chance x2. Inactive entries: GoblinCamp2_1 (never placed: no biome area)
25	Death Plains	Adds creatures Deathsquito; removes creatures Lox, Goblin; removes vegetation entries birch2_aut_heath, heathrockpillar; adds locations TarPit1 (50), TarPit2 (20), TarPit3 (100); removes locations GoblinCamp2, StoneTower1, StoneTower3, StoneHenge1, StoneHenge2, StoneHenge3; creature level-up chance x2
26	Kalhygge Black Forest	Adds vegetation stubbe, Pinetree_01_Stub; removes vegetation entries firtree_many_blackforest, firtree_blackforest, Pinetree_01_blackforest, firtree_small_blackforest
27	Rockless Mistlands	Adds vegetation cliff_mistlands1, cliff_mistlands2, rock_mistlands1, YggaShoot_small1; removes vegetation entries cliff_mistlands1, cliff_mistlands2, rock_mistlands1
28	Trees Mistlands	Adds vegetation YggaShoot1, YggaShoot_small1, YggdrasilRoot
29	Swords Mistlands	Adds vegetation giant_sword1, giant_sword2, giant_helmet1, giant_helmet2
30	Hare Mistlands	Adds creatures Hare
31	BroodSwarm Mistlands	Adds creatures SeekerBrood

What this means for map authors

- **Islands and mid-sized patches host alt biomes.** Most alt biomes want a region with an edge count of roughly 66 to 200, which for a round region means a radius of about 150 to 425 m (about 30 to 80 px across on a 2048 px map). The Mountain alt biomes want larger regions, a radius of about 425 to 640 m. *Kalhygge Black Forest* wants small ones, about 45 to 175 m.
- **Huge regions get none.** A continent-sized, single Meadows region has an edge count far above every Meadows window, so it hosts no Meadows alt biomes at all. The edge count also includes the rim of every hole in a region: a lake painted as Ocean, or a patch of another biome inside it. A large region full of holes is "huge" too.
- **Regions around the centre get none.** Distance is measured from the mean of the edge points, not from the nearest point. A region that surrounds the world centre, such as a ring of Meadows around the spawn, has its mean edge position near the centre and fails every minimum distance (500 to 2,000 m).
- **Edges must sit above water.** A sector's height is the midpoint of its lowest and highest edge heights, and it must be at least 30 m. The biome map, not the coastline, decides where a sector ends. A land biome painted out into the sea therefore has underwater edge points that drag this down, and a low swamp whose edges sit below the waterline fails.
- **Ragged outlines and speckles cost you.** Noisy borders add edge points, which can push a region over the maximum. Stray pixels of another biome make tiny sectors of their own and add edge points to their surroundings. Soft, anti-aliased biome edges also snap to a third biome (see [Biome map](#)).
- **Ashlands, Deep North and Ocean are global.** Each is one sector for the whole world. Only *Lantern* lists Deep North, and the global Deep North sector passes its edge window (66 to 198) only if the whole Deep North is small.
- **Plan for the minimums.** Alt biomes with a minimum of 1 or more take the first qualifying sectors regardless of chance. If your map offers too few qualifying regions, the log shows the *Placed X/min-max* warning, which is harmless.
- **When the effects appear.** Added locations are placed when the world's locations are generated, at creation. Vegetation is placed when a zone is first generated, so zones that already exist keep what they had (Better Continents can reset them after a [bc](#) change: see [Debug](#)); the game's own `altbioms` command notes that modifiers only appear in unexplored zones. Creature, weather and level-up changes apply live. With [Skip Default Locations](#) on, the added locations are skipped along with all other default locations.
- **Checking the result** (cheat commands, so `devcommands` first): `biomeinfo` prints the sector you are standing in (edge size, centre, height range, distance, alt biomes), `altbioms` lists every sector that received alt biomes, and `findbiome <text>` pins the centres of sectors whose biome or alt biome matches the text, nearest first.

New in BC 0.8.1: You no longer have to design your map around these rules. Plant the alt biomes you want where you want them (next section), and use the random-placement controls to loosen the rules on the rest of the map: for example a larger [Region Size Scale](#) for big hand-drawn regions, or [Mean Sector Height](#) for regions whose biome paint runs out into the sea. `bc ab info` shows why each alt biome did or did not place, and `bc ab here` how each one fared on the region you stand in.

Planting alt biomes with colours (BC 0.8.1)

New in BC 0.8.1: This section is new.

Better Continents 0.8.1 lets a map author **plant** alt biomes with colours, the way the biome map plants biomes. A second, optional image, the **alt-biome map** ([altbiomemap.png](#)), is laid over the world exactly like the biome map. Its **legend** ([altbiomemap.txt](#), beside the image) says which alt biomes each colour plants. Black and transparent pixels are unplanted: the game's own placement decides there. A line **Name: at x, z** plants the whole region under a world position instead of a painted area.

Every planted area becomes a region of its own and gets the alt biomes its colour names. The game's own random placement still runs on the land you did not plant, unless you switch it off (see [Modes](#)).

Setting up the alt-biome map

- Set [Altbiomemap File](#) in the config section [08 BetterContinents.AltBiomes](#). When the [Project Directory](#) ([Directory](#), section [00 BetterContinents.Debug](#)) is set, only a file named [altbiomemap.png](#) in that folder is used, as for every map.
- The legend is [<image name>.txt](#) beside the image. If it is missing, Better Continents writes it with the default palette below and short instructions.
- The image is square, of any size, and covers the same square as every other map: 21,000 m × 21,000 m centred on the world centre (on a new world, version 12, as large as the world: 2 × (World Size + Edge Size), which is 21,000 m at the default sizes), with the top of the image north. Use PNG: a lossy format shifts colours.
- Like every map, it is baked into the world when the world is created, so it travels with the world, with presets and to clients. What is baked is the decoded map, not the PNG: colours are matched once, when the map is baked, and every server and client reads the same result. The alt-biome names are looked up when the world loads.
- It works with or without a biome map, so procedurally generated biomes can be planted too. It does not change the biome map: [biomemap.png](#) and [biomemap.txt](#) keep their meaning.
- Editing the image or the legend later changes nothing until you bake the map again in game, with [bc reload ab](#) or [bc ab fn](#) (see [Reports and commands](#)).

The legend

One instruction per line:

```
<alt biome>[ + <alt biome> ...]: <colour>    plant these alt biomes where the
<alt biome>[ + <alt biome> ...]: at <x>, <z>    image has this colour
none: <colour>                                plant them on the whole region at
                                                world position x, z
                                                a protected region: no alt biome,
                                                planted or random
```

Examples:

```
Dark Meadows: 2D4613                plant Dark Meadows where the image is #2D4613
Dark Meadows + Lantern: 0080C0      two alt biomes on one colour
Lantern: 0080C0                     ...the same colour on another line stacks the same way
*Mistlands: 7F3FBF                  every Mistlands alt biome that fits
!Dark Meadows: 7A8B9C               force it, even on a Black Forest region
none: C030F0                        keep this area free of alt biomes
Troll Black Forest: at 2750, -1210  the whole region under (2750, -1210)
Bat Swamp: @ 3728, 7088              short form
```

- **Names** are the game's internal alt-biome names (the names in the tables of this chapter), matched case-insensitively. A name that is not one of the 32 vanilla names is noted when the map is baked ("fine if another mod adds it"); a name the game does not have when the world loads is warned about and plants nothing.
- ***** is a wildcard: ***Mistlands** plants **every** alt biome whose name matches and that fits the land, subject to the content rules (see [What planting does](#)). ***Plains** plants Lox Plains only: Goblin Plains and Death Plains are incompatible with it and are refused.
- **+** stacks alt biomes on one colour. Listing the same colour on several lines does the same.
- **!Name** forces that name past the content rules (disabled, wrong base biome, incompatible), and makes the colour claim every base biome.
- **none** cannot be combined with names: the **none** is ignored, with a warning.
- **Colours** are **RRGGBB**, **#RRGGBB**, **RRGGBBAA**, **#RRGGBBAA**, **r,g,b** or **r,g,b,a** (decimal). An alpha component is accepted and ignored. Black (**000000**) is reserved for unplanted land and is refused.
- **Points** are **at x, z** or **@ x, z**: world coordinates in metres (x east, z north), with **.** as the decimal point.
- **Comments:** **#** starts a comment at the start of a line, or where it has whitespace on both sides (or ends the line), so **Dark Meadows: #2D4613** is still a colour.
- A colour within 40 RGB units of another legend colour is warned about: pixels between them could go either way.
- A legend holds at most 254 entries: distinct colours plus point lines.

Which pixels are planted

Pixels are matched once, when the map is baked (at world creation, and by **bc ab fn** and **bc reload ab**). Distances are Euclidean, over R, G and B.

Pixel	Result
alpha below 128	unplanted
within 20 RGB units of a legend colour, and nearer to it than to black	that legend line (the nearest colour wins; on a tie, the first in legend order)
black at least as near as the nearest legend colour	unplanted
within 20 of neither a legend colour nor black	unplanted; a warning lists the five most common such colours, each with the nearest legend colour and its distance

Then, at every world load, each 12 m grid point takes the result of the nearest pixel. Nothing is planted outside the image or beyond the sampled disc. A colour **claims** a point only if one of its alt biomes (that exists and is enabled) belongs to the point's base biome, or a name is forced, or the colour is **none**. Painted points that a colour does not claim stay unplanted and open to random placement, so painting past a biome edge is harmless: if you paint *Dark Meadows* roughly over an island, only the island's Meadows change, and its Black Forest and the Ocean around it are left alone.

The 20-unit tolerance absorbs small colour drift from image editors. The default palette keeps every pair of its colours more than twice that far apart, so a pixel can never match two of them.

Default palette

These are the 32 colours Better Continents writes into a new legend, one per vanilla alt biome. They are generated from Better Continents' own code ([palettes/palette.json](#) in its source repository), and grouped as the palette groups them, by the base biomes each alt biome plants on. *Plants on* is the alt biome's own biome setting in Valheim 1.0.

Every pair of alt-biome colours, and every alt-biome colour and every base-biome colour of the [biome map](#) legend (black and white included), is more than 2×20 RGB units apart. The closest pairs are Rock Black Forest and Trees Mistlands (52.4) and Abomination Swamp and Mistlands (54.6). The overlay therefore stays easy to tell apart from the biome map when you paint both as layers of one project file. The palette's ten base-biome colours are the biome map's, listed on the [Biome map](#) page. The palette file for paint programs and the printable chart hold the same colours; see [Painting colour maps](#).

Meadows (6)

Swatch	Alt biome	Hex	R, G, B	Plants on
	Dark Meadows	2D4613	45, 70, 19	Meadows
	Peaceful Meadows	ADFFDA	173, 255, 218	Meadows
	Dandelion Meadows	E5C54B	229, 197, 75	Meadows
	Raspberry Meadows	C2185B	194, 24, 91	Meadows
	Smalltree Meadows	6EC03D	110, 192, 61	Meadows
	Birch Meadows	CCFFAC	204, 255, 172	Meadows

Black Forest (7)

Swatch	Alt biome	Hex	R, G, B	Plants on
	Troll Black Forest	2C7B76	44, 123, 118	Black Forest
	Root Black Forest	6F5E32	111, 94, 50	Black Forest
	Ruin Black Forest	9D6C4B	157, 108, 75	Black Forest
	Rock Black Forest	5A5264	90, 82, 100	Black Forest
	Pinetree Black Forest	004754	0, 71, 84	Black Forest
	Blueberry Black Forest	4A5CB6	74, 92, 182	Black Forest
	Kalhygge Black Forest	A9AE34	169, 174, 52	Black Forest

Swamp (4)

Swatch	Alt biome	Hex	R, G, B	Plants on
	Hut Swamp	B1332D	177, 51, 45	Swamp
	Bog Swamp	6E2143	110, 33, 67	Swamp
	Bat Swamp	382B41	56, 43, 65	Swamp
	Abomination Swamp	95B17E	149, 177, 126	Swamp

Mountain (3)

Swatch	Alt biome	Hex	R, G, B	Plants on
	Wolf Mountain	93C7BC	147, 199, 188	Mountain
	Drake Mountain	5AAAC2	90, 170, 194	Mountain
	Fortress Mountain	B697AF	182, 151, 175	Mountain

Plains (3)

Swatch	Alt biome	Hex	R, G, B	Plants on
	Lox Plains	CC605F	204, 96, 95	Plains

Swatch	Alt biome	Hex	R, G, B	Plants on
	Goblin Plains	FF7622	255, 118, 34	Plains
	Death Plains	671E07	103, 30, 7	Plains

Mistlands (5)

Swatch	Alt biome	Hex	R, G, B	Plants on
	Rockless Mistlands	D99FE8	217, 159, 232	Mistlands
	Trees Mistlands	472577	71, 37, 119	Mistlands
	Swords Mistlands	8A7FDB	138, 127, 219	Mistlands
	Hare Mistlands	D56EBB	213, 110, 187	Mistlands
	BroodSwarm Mistlands	8E2F8E	142, 47, 142	Mistlands

Several base biomes (4)

Swatch	Alt biome	Hex	R, G, B	Plants on
	Mushroom	FF969C	255, 150, 156	Meadows, Black Forest
	Lantern	F2A300	242, 163, 0	Meadows, Black Forest, Swamp, Mountain, Plains, Mistlands, Deep North
	Bones	F8E1B6	248, 225, 182	Swamp, Plains, Mistlands
	Menhir	DDA776	221, 167, 118	Meadows, Plains

- No vanilla alt biome changes the biome name shown in game, so a planted region still says, for example, "Meadows". Players notice it through what grows, spawns and gets placed there. See [the 32 alt biomes](#) for what each one changes.
- Nothing targets Ashlands or Ocean, and *Lantern* is the only alt biome for Deep North.

What planting does

- **Planted areas become regions of their own, never merged.** Each 4-connected patch of one colour inside one of the game's regions becomes a region of its own. Two patches of one colour in the same game region are two regions, and a patch never joins a neighbouring region. On Ashlands, Deep North and Ocean, which the game treats as one world-wide region each, all patches of one colour form **one** region. What is left of a game region after its patches are taken out stays one region, measured again over what is left.
- **Random placement elsewhere is unchanged.** While the game places alt biomes at random, the planted regions are hidden from its lists, so the alt biomes you did not plant land where they would have landed without the planting, except in the regions the planting touched and where the quota rule below applies.
- **Point lines split nothing.** A line `Name: at x, z` applies to the whole region under the position: a planted region, what is left of a game region, or, on Ashlands, Deep North and Ocean, the whole unplanted world-wide region.
- **Planted alt biomes count toward the game's minimum and maximum.** Planting happens first, and the game counts every region an alt biome already has when it decides whether to place more (see the table below). Planting itself is not capped: plant three Fortress Mountain regions and all three get it; the game then places none.
- **Planting ignores the game's occurrence rules:** region size, distance from the centre, average height, world position bounds, neighbour rules and chance. You have chosen the place.
- **Planting keeps the game's three content rules,** because breaking them is almost always a mistake: an alt biome the game has disabled is not planted; an alt biome is only planted on the base biomes it belongs to (its colour does not even claim other base biomes); and an alt biome that is incompatible

with one already on the region is not planted, first come first served in legend order. The disabled and incompatible cases are logged as warnings. **!Name** overrides all three for that name.

The quota rule with the game's own numbers (from [the 32 alt biomes](#)): the game's random placement runs while *planted* + *placed* is below the maximum, and ignores the chance while it is below the minimum.

Planted	Fortress Mountain (1-2)	Lox Plains (0-1)	Dark Meadows (2-5)
0	at least 1, at most 2 random	at most 1 random	at least 2, at most 5 random
1	at most 1 more random	none	at least 1, at most 4 more random
2	none	none	at most 3 more random
3	none (all 3 planted)	none	at most 2 more random

"At least" holds only where enough regions pass the game's tests. **Amount Multiplier** and the **min** and **max** overrides change these numbers, and planted regions count against the changed ones. An alt biome of several base biomes (*Lantern*, 3-5) counts all of them together. On Ashlands, Deep North and Ocean one colour is one region, and counts once.

When planting fails

Zones generated with the wrong alt biomes are permanent, so a **planting error stops the world load** with a clear message instead of carrying on without the planting. An error is an alt-biome map in the world's settings that cannot be read, or any failure while sampling the map, splitting the regions or applying the planted alt biomes.

- A dedicated server logs the error and quits (exit code 1) without saving the world. A host logs out without saving, and a client disconnects.
- In mode **Off** nothing is planted, so such a world still loads.
- Content problems are not errors: an unknown name, a disabled or incompatible alt biome, or a colour that matches no legend line is logged as a warning and simply not planted.
- The world carries its own baked copy of the map, so editing the image or the legend cannot repair a world whose stored map is damaged. Restore the world's Better Continents settings file from a backup (the previous save's copy ends in **.old**). Any other failure is a bug to report, with the log.
- During a live edit with the **bc** commands, a planting error keeps the previous regions and placement instead.

Multiplayer

The alt-biome options and the baked alt-biome map travel to clients inside the world's Better Continents settings, like every other map. Each client builds its own grid and regions from them. The server then sends its **placement**, which region has which alt biomes, and the client applies it over its own, so every region both machines agree on carries the server's alt biomes, random ones included.

Both sides compute two hashes, one of the region grid and one of the placement. The client logs whether they match the server's and reports its hashes back, and the server logs the result for each client. A difference is a warning, never a kick: on a client whose grid differs, the regions that still match get the server's alt biomes and the rest get none.

Modes

Set with **Mode** in the config (for new worlds), or with **bc ab mode** in game:

Mode	Planted regions	Game's random placement
Random (default)	planted	on unplanted land, under the world's options
PlantedOnly	planted	skipped
Off	nothing; the map is not even sampled	skipped: no alt biome anywhere

A **none** region is protected in every mode: nothing is planted on it, and random placement stays off it. **Off** also clears alt biomes already assigned, and an unreadable alt-biome map does not stop the load in that mode. Without alt biomes, the locations they add, such as the wood villages of *Dark Meadows*, have nowhere to go.

New in BC 0.10: **Off** means no alt biomes, not no grid. Valheim builds its biome grid for every world, and every terrain chunk takes its biomes from it, so the grid exists in every mode; **Off** only keeps alt biomes off it.

Controls for random placement

The settings in `08 BetterContinents.AltBiomes` are defaults for **new** worlds. When a world is created they are baked into its settings, like the maps, and they are never read from the config again for that world. The world owner changes them in game with the `bc ab` commands, which save with the world. A world whose settings hold no alt-biome options, which includes every world made before 0.8.1, behaves as with 0.8.0: mode **Random**, grid **Vanilla**, the world seed, no multipliers and no overrides.

These settings steer **only the game's random placement**; planted regions ignore them.

Setting	Console	Default	Effect
Fixed Seed	<code>bc ab seed [value], bc ab reroll [seed]</code>	empty	The seed for the game's random placement. Empty or world is the world seed (vanilla). A whole number is used as is; any other text is hashed like a world seed name. The same map then gets the same random layout whatever the world seed. <code>bc ab reroll</code> sets a new fixed seed: a random one, or the one given.
Chance Multiplier	<code>bc ab chance [0-10]</code>	1	Multiplies every alt biome's chance (the result is capped at 1).
Amount Multiplier	<code>bc ab amount [0-10]</code>	1	Multiplies every alt biome's minimum and maximum count, rounded to whole numbers.
Region Size Scale	<code>bc ab regionscale [0.1-50]</code>	1	Multiplies every alt biome's edge-count window. The game only gives alt biomes to regions roughly 0.1 to 2.4 km across; big hand-drawn regions usually need 2 to 10.
Distance Scale	<code>bc ab distancescale [0-10]</code>	1	Multiplies every alt biome's minimum distance from the centre, and its world position bounds.
Min Sector Thickness	<code>bc ab thickness [0-20]</code>	0	Regions thinner than this (area divided by edge count, in 12 m cells) never get a random alt biome. 0 is vanilla; 2 filters out the slivers an anti-aliased biome map leaves along its borders.
Mean Sector Height	<code>bc ab meanheight [true false]</code>	false	Measures a region's height as the mean over the whole region, instead of the game's midpoint between the lowest and highest edge heights. Helps maps whose biome paint runs into the sea, where the edge is under water and the game's measure sinks below the 30 m that every alt biome requires.
Fix Neighbour Check	<code>bc ab neighbourfix [true false]</code>	false	Uses a corrected required/forbidden-neighbour test. The game's is broken: any required neighbour makes every region fail, and the forbidden-neighbour test looks for the wrong biome except for Meadows and Swamp. No vanilla alt biome uses it; alt biomes from other mods may.
Overrides	<code>bc ab set, bc ab clear, bc ab overrides</code>	empty	Per-alt-biome overrides of the random placement; see below.

Min Sector Thickness, **Mean Sector Height** and **Fix Neighbour Check** switch the eligibility test to Better Continents' copy of the game's test, with the change; with all three off, the game's own test runs.

With every one of these controls at its default, random placement is exactly the game's.

Overrides use the syntax `Name: key=value, key=value; Other Name: key=value`, in the config and in `bc ab set <name|pattern|*> <field> <value>`, which sets one field (default clears it). `bc ab clear [name|pattern|*]` clears one entry's overrides, or all of them without a name, and `bc ab overrides` prints them.

Key	Value	Replaces the alt biome's
<code>enabled</code>	<code>true, false, 1, 0</code>	enabled flag (random placement only)
<code>chance</code>	0 to 1	chance
<code>min, max</code>	0 to 10000	minimum and maximum count
<code>mindist</code>	0 to 1000000 (m)	minimum distance from the centre
<code>minedge, maxedge</code>	0 to 100000000 (cells)	edge-count window
<code>minheight, maxheight</code>	-100000 to 100000 (m)	height window
<code>ignorebounds</code>	<code>true, false</code>	world position bounds (<code>true</code> switches them off)

- Values out of range are clamped. An empty value or `default` clears the field.
- A name may contain `*` wildcards, and `*` alone applies to every alt biome. Names are compared case-insensitively.
- Precedence, field by field: the exact name, then the matching patterns (more literal characters first, then in ordinal order), then `*`.
- An override replaces the multiplied value for its field: `chance=0.5` is 0.5 whatever `Chance Multiplier` says.
- If the resulting maximum is below the minimum, the maximum is raised to the minimum. A disabled alt biome gets minimum 0, so the game does not warn that it placed too few.
- Overrides never touch planted regions: `Fortress Mountain: enabled=false` stops the game placing Fortress Mountain at random, and planted Fortress Mountain still works.

Examples: `Fortress Mountain: enabled=false, *Mistlands: chance=0.5; Hare Mistlands: max=1, *: minedge=0, maxedge=100000`.

One more setting changes the region grid itself, so it applies to planted and random alt biomes alike: `Grid(bc ab grid [WorldEdge|Vanilla], default WorldEdge)`. With `WorldEdge`, when the edge of the world (World Size + Edge Size) is inside 10,500 m and Map Edge Drop-off is on, grid points beyond the edge are marked as outside-the-world ocean, so alt biomes, and the location candidates the game picks from the grid, cannot land beyond the edge. `Vanilla` always samples the 10,500 m disc. `Grid` has no effect when Expand World Size owns the grid.

New in BC 0.10: `Grid` has no effect on a new world either: that world's grid is laid out to the world and reaches its edge (at the default World Size and Edge Size the `WorldEdge` cut-off could not apply anyway).

Reports and commands

When a world loads, Better Continents writes an alt-biome summary to the log. It names the mode, the placement seed and the grid, counts the regions and those with alt biomes (planted and random), and gives the grid and placement hashes. It then lists what each legend line planted, one line per base biome, the biomes absent from the map, and, for each alt biome, why it did or did not place (with "+N planted (counted toward the maximum)" where planting counts). The game's own `biomeinfo`, `altbioms` and `findbiome` commands read the same regions.

The `bc ab` commands are part of Better Continents' `bc` command: a cheat command (cheats come from `devcommands`, which Better Continents' *Debug Mode* types for you when you spawn) that runs on the machine that hosts the world. `bc ab help` lists them. Edits change the loaded world's settings and are saved with the world. They redo only as much of the grid, regions and placement as they affect, and then regenerate the zones (see [Debug](#)); connected clients keep their placement until they reconnect. A value command without a value prints the current one.

Command	What it does
<code>bc ab info</code>	A summary of this world's alt biomes: why each did or did not place, what each legend line planted, and up to 40 planted regions.
<code>bc ab list [filter]</code>	Up to 60 regions with alt biomes. The filter is <code>planted</code> , <code>random</code> , <code>all</code> , a biome name, or part of an alt-biome name.
<code>bc ab here</code>	The region you stand in, what was planted on it, and how each alt biome of its biome fared.
<code>bc ab show [filter]</code> , <code>bc ab hide</code>	Map pins on every region with an alt biome (optionally filtered by alt-biome name), and removing them.
<code>bc ab export</code>	Writes <code>altbiomes-<time>.png</code> and a <code>.txt</code> report to <code><save folder>/BetterContinents/<world name>/. The image shows the region grid, north up, with alt-biome regions tinted in their alt biome's colour, planted regions striped magenta and region borders darkened.</code>
<code>bc ab hash</code>	This machine's grid and placement hashes.
<code>bc ab names [filter]</code>	The game's alt biomes, with their default colours and random-placement rules.
<code>bc ab rebuild</code>	Rebuilds the grid, regions and placement from the current settings.
<code>bc ab fn [path]</code>	Sets the alt-biome map (a full path, a directory or a file name) and bakes it with its legend. Clearing the field in the Better Continents settings window (the Better Continents button in the Esc menu or on the large map; Alt+F8 there does the same) removes it.
<code>bc reload ab</code>	Re-reads the alt-biome map and its legend from their files and bakes them again. <code>bc reload all</code> includes it.
<code>bc ab mode [Random PlantedOnly Off]</code>	Sets the mode.
<code>bc ab grid [WorldEdge Vanilla]</code>	Sets the grid.

The commands for the random-placement controls are in the [table above](#).

For every player, on a client or on a host, there is a separate command:

Command	What it does
<code>bc_altbiomes</code>	The hashes and whether they agree with the server's, and the region you stand in.
<code>bc_altbiomes here</code>	The region you stand in, in full.
<code>bc_altbiomes names [filter]</code>	The alt-biome names and their default colours. This works on the main menu too.
<code>bc_altbiomes hash</code>	The hashes and whether they agree with the server's.
<code>bc_altbiomes list [filter]</code>	Up to 200 regions with alt biomes, with the same filters as <code>bc ab list</code> . It reveals where they are, so on a client it needs <code>devcommands</code> , like the game's own <code>altbioms</code> .

As with every change in game, zones that were already generated keep what they had until they are regenerated. Better Continents regenerates them after each `bc` change, apart from the zones around something a player built or worked, a tombstone, another player or you inside a dungeon, and `bc regen` does it on demand; see [Debug](#) and [Settings](#).

Limits

- A legend holds at most 254 entries (distinct colours plus point lines). Images can be up to 16384 × 16384.
- The grid is 12 m: a patch narrower than a cell or two can vanish or break into several regions. Paint patches at least a few cells wide.
- Only the sampled disc has regions: 10,500 m, the edge of the world with **Grid** set to **WorldEdge**, Expand World Size's radius, or, on a new world laid out to its size, the world's own edge. Planting beyond it does nothing.
- Ashlands, Deep North and Ocean are one region per colour: two Deep North areas painted with the same colour are one region, and count once toward the maximum. Use two colours to make two regions.
- Planting chooses alt biomes, not terrain or base biomes.
- Zones the game has already generated keep the vegetation and locations they got. Plant before a world is explored. (Better Continents regenerates zones after a **bc** change: see [Debug](#).)

Compatibility

- **Vanilla worlds**, without Better Continents settings, behave exactly as before. The only 0.8.1 patch that acts on them is the grid fix for Expand World Size, and only on a grid that Expand World Size has resized.
- **Existing Better Continents worlds** keep the same regions and the same random alt biomes as with 0.8.0, and their settings are saved byte for byte as 0.8.0 saves them. What does change for them are the 0.8.1 fixes: Deep North weather on worlds with a biome map, in-game edits with the **bc** commands (see [The cache file](#)), land beyond 10,500 m on worlds with Map Edge Drop-off off, and locations that accept several biomes.
- **Worlds in 0.10**. Every existing world keeps the regions and the random alt biomes it had in 0.9.4. A new world (version 12) with another World Size or Edge Size has a grid laid out to its size (see [How Valheim assigns them](#)).
- **Worlds that use an alt-biome feature** (an alt-biome map, or any option that differs from the 0.8.0 behaviour) need 0.8.1 or later. Better Continents 0.8.0 stops reading the world's settings at the first key it does not know and loads the world *without* Better Continents: it leaves the settings file alone, but zones generated in that session get vanilla terrain. A new world whose World Size + Edge Size is under 10,500 m counts as using a feature, because **Grid** defaults to **WorldEdge**. In multiplayer this cannot happen by accident, because server and clients must run the same Better Continents version.

8 Export and Import

New in BC 0.9.0: This page is new in this edition, and all of its text is edition text. Export, import, the export HUD, config that applies while the game runs, and Biome precision are all new in Better Continents 0.9.0; none of it existed in this edition's earlier chapters.

Since 0.9.0, Better Continents can turn the world you are standing in back into a set of maps, and turn a folder of maps — an export, or one you painted by hand — into a choice in the New World screen. Between them they cover two jobs the rest of this guide does not: taking a copy of a world you already have, and loading a finished set of maps without editing your config file by hand.

Exporting the world you are in

`bc_export`, typed into the console (**F5**), writes the loaded world's heightmap, biome map, location map, forest, heat, alt-biome, lava, moss and paint maps into `<your save data>/BetterContinents/<world name>/export-<date and time>/`, together with:

- `export.cfg` — the Better Continents settings that rebuild the world from those maps,
- `README.txt` — the ways to make a new world from the export, written for someone who has never done it,
- `manifest.json` — the same numbers as machine-readable JSON,

and, unless you turn it off, a New World preset named after the world and the time, ready to pick the next time you create a world.

`bc_export` is not a cheat command: it works for any player, subject to your server's **Allow Export** setting. Options — a size in pixels, the Heightmap Amount and Sea Level to encode heights for, which maps to include, and more — can be given on the command line (`bc_export help` lists them) or in the **export window**: press **F7** in a loaded world to open it, or **F9** for a small status box. Both are off until you turn on **Hud** under `[09 BetterContinents.Export]`, in the config or in BepInEx Configuration Manager. On a server, the host's **Hud** and **Allow Export** settings apply to every connected client too.

An export made by a client only knows the locations the server has shown that player on the map so far, so its location map is left incomplete on purpose (the game is left to place the rest). Export from the host, or from the dedicated server's own console, for a complete location map.

New in BC 0.10: An export encodes its heights for **Heightmap Amount 1** unless you say otherwise (it was 2 in 0.9.x), the same default as everywhere else in Better Continents. On the game's own height scale that spans **-30 m to 170 m** (the sea is at 30 m, so that is 60 m below the water to 140 m above it), and ground higher than that is clipped; the export says how many pixels it had to clip. `bc_export amount=2`, the Heightmap Amount field of the export window, or **Default Heightmap Amount** under `[09 BetterContinents.Export]` store **-30 m to 370 m** (up to 340 m above the water) instead, which keeps every vanilla mountain at the price of coarser steps (see [Heightmap](#)). A `BetterContinents.cfg` that still holds the 0.9 default of 2 for **Default Heightmap Amount** is set to 1 once, and the log says so.

The export also records the Amount and Sea Level its heights are encoded for **inside heightmap.png** (a PNG text chunk), as well as in `export.cfg` and `manifest.json`. A new world that reads the heightmap at other values warns in the log and `bc info` shows the record, so a heightmap that wandered away from its `export.cfg` can still be recognised.

`bc_export server ...` now also answers the admin who ran it on a dedicated server, and tells them when the export ends.

Importing an export

`bc_import` (also not a cheat command, and it works from the main menu as well as in a world) turns a folder back into something the New World screen can build from:

- `bc_import` on its own takes the newest finished export of the world you are in; from the main menu, or if that world has none, it falls back to your last export this session and then your last-played world's newest export. It builds a New World preset and selects it.
- `bc_import list` numbers every export you have, newest first; `bc_import <number>`, `bc_import <world name>` and `bc_import <folder>` each pick one a different way.
- Adding `config` (for example `bc_import 2 config`) copies the folder's settings into `BepInEx/config/BetterContinents.cfg` instead — your old file is kept beside it — and selects **From Config**, so every world you create afterwards reads that folder's maps as they are *then*. This suits a folder of maps you are still editing; a preset is simpler once you are done.

The export window's Import tab has the same two choices, as the buttons **Make preset** and **Use as config**.

New in BC 0.9.4: There is one more way, with no console and no preset: set `[00 BetterContinents.Debug] Directory` to the export folder and create a New World with **From Config**. Better Continents then lays the folder's `export.cfg` over `BetterContinents.cfg` for that world, as an import does, without changing either file; `export.cfg`'s settings win, so edit or delete it to use values of your own. This applies after `bc_import ... config` too, which also points **Directory** at the folder: change such a setting in `export.cfg`, not in `BetterContinents.cfg`. Before 0.9.4 a world loaded through **Directory** alone took only the maps and kept the config's default Heightmap Amount of 1, which drowned the heightmap of a 0.9.x export (stored for Amount 2) almost entirely. See [Project](#).

Importing, like editing any map, only changes what the *next* New World is built from. The world you are standing in keeps the maps it was created with.

Config that applies while the game runs

`[09 BetterContinents.Export]` is the group of settings that takes effect immediately, including on a client whose server changes it; `Settings Transfer Rate` and `Map Memory` (in `[07 BetterContinents.Misc]`) apply at once too. Better Continents 0.9.0 also watches `BetterContinents.cfg` itself and re-reads it whenever it changes on disk, not only once when the game launches. World-generation settings (Heightmap Amount and the rest) still only matter for a world at the moment it is created, but you no longer have to quit and relaunch the game after editing the file: save your edit, then create the next world. `Override version` is the exception among them: it is read at every save, so an edit counts for the next save of a world that is loaded (see [Debug](#)).

Biome precision

[03 `BetterContinents.Biomemap`] **Biome precision** (console `bc b p`, 0 to 5, and up to 31 on a new world, version 12) works again from Better Continents 0.9.0: see [Biome map](#) for what it does.

Joining a Better Continents world: the download, and how to shorten it

A player who joins a Better Continents world receives its settings and image maps from the host or the dedicated server before the join finishes; their game caches them, so the transfer happens once per world revision. Valheim pins every Steam connection to about 150 KB/s, so a detailed world (tens of megabytes) can take over a minute to arrive. Better Continents 0.9.0 adds two ways round that:

- [07 `BetterContinents.Misc`] **Settings Transfer Rate** — `Vanilla`, `KB256`, `KB384`, `KB512` (the default), `KB768`, `MB1`, `MB1_5`, `MB3` or `Unlimited` (100 MB/s). The sending machine sets Steam's send rate for that one connection to the value for the transfer only, then restores Valheim's own. Steam sends at exactly the rate set, with no congestion control, and the transfer itself moves about 4 MB/s at most: an 11.8 MB world took 78 s at `Vanilla`, 23 s at `KB512` and 3 s at `Unlimited` on a local dedicated server. Only the server's (or host's) value counts; a client's has no effect, and a PlayFab (crossplay) connection cannot be changed at all. The log records the rate used and the transfer's size, time and speed.
- `bc_cache` — `bc_cache export`, on the machine that runs the world, writes its settings as a `<world>-<id>.bcworld` file (with a `.txt` note beside it) in `BetterContinents/<world>/`; a player runs `bc_cache import <file or folder>` in the main menu, or drops the file into `BepInEx/config/BetterContinents/seed/`, and joins with no download at all. Better Continents also imports every `.bcworld` it finds under `BepInEx/plugins/` when it starts, so a mod pack holding nothing but that file pre-seeds every player who installs it. `bc_cache list` shows the cache; an import never overwrites an entry, and the id is always recomputed from the file's content. Better Continents 0.9.x refuses the `.bcworld` file of a new world (a settings package of version 12) as a bad header; a server and its players must run the same version in any case.

Compact Maps (experimental)

New in BC 0.10: Every world holds its maps in memory as tiles (see [Image maps](#)). [07 `BetterContinents.Misc`] **Compact Maps** goes further, for a world of very large maps. It is **experimental** and **off by default**.

What it does. A **new world** made while Compact Maps is on keeps its maps compressed in memory, in tiles of 128 × 128 pixels, and decodes a tile only when the world first reads it. It saves and sends the maps compressed, too. Every map reads exactly as it would without. For a real set of a 10,501 px heightmap, forest map and biome map, the world file shrinks from 126 MB to 10.5 MB, and a loaded world holds about 21 MB instead of about 99 MB (about 90 MB once every tile has been decoded). A player who joins downloads the smaller settings as well.

When it counts. The setting is read only when a world is made, with **From Config**, with `bc_import`, or from a Directory's `export.cfg`, and only for a world of the newest settings version (12). A world keeps it for good: turning it on later changes nothing in a world that exists.

The price. Better Continents 0.9 cannot read a world made with Compact Maps: it would generate the terrain as vanilla. Leave it off for a world you want people on 0.9 to be able to open.

Map Memory ([07 `BetterContinents.Misc`], default `512`, from 64 to 65536 megabytes) is how much memory this machine lets the decoded tiles of a compact world's maps take. Past it, the tiles read least recently are dropped and decoded again when they are read again. 512 holds every tile of a large world's maps, so each is decoded once; a server short of memory can use less (each player's surroundings take about a megabyte). It has no effect on any other world, which holds its maps

decoded, and it applies at once.

The full walkthrough

This page is the short version. [BetterContinents-Export-Guide.pdf](#), included in the same package as this guide, is an illustrated, step-by-step walkthrough of exporting and importing, written for players new to Better Continents, with every console form, every file the export writes, and what to do when something goes wrong.

Appendix A

Changes in this edition

Updated for Valheim 1.0 / BC 0.8.0: This appendix is new in this edition. It lists every substantive change made to the original guide, first for the BC 0.10 update, then the BC 0.9.4 update, then the BC 0.9.1 update, then the BC 0.9.0 update, then the BC 0.8.1 update, and finally, page by page, for the Valheim 1.0.15 / BC 0.8.0 update. Each change is also marked in place, with a *New in BC 0.10*, a *New in BC 0.9.4*, a *New in BC 0.9.0*, a *New in BC 0.8.1* or an *Updated for Valheim 1.0 / BC 0.8.0* box.

BC 0.10 update (2026-10-04)

Every existing world and preset keeps its terrain, biomes and locations exactly as in 0.9.4, and a world's settings are saved as 0.9.4 saved them. What else changes for them is listed under *Every world*. Everything under *New worlds* belongs to new worlds, those of settings version 12, which is what 0.10 gives a world it creates, and never reaches a world marked with an older version. A preset keeps the version it was saved with, so it makes the world it always made: the four presets that ship with the mod are version 7 and make version 11 worlds. A new world made from map files of your own is a version 12 world, which reads them the 0.10 way; setting [Override version](#) to 11 before you make it gives a version 11 world, which gets none of the new-world changes, as 0.9.4 would have made it. While [Override version](#) is set it is also the version every world is saved in and sent to joining players, so leave it empty.

Which version is my world? [bc info](#) prints the settings version first: **Version 11** is a world of the 0.9 kind, **Version 12** a new world. A world made from an export is version 12 when the export's maps span what its own World Size and Edge Size give (every export of a version 12 world, and every 0.9.x export of a world of the normal size), and otherwise version 11: an export of a world resized under 0.9.x, or made under [Expand World Size](#) at another size, gets none of the new-world changes. Nothing converts an existing world from version 11 to 12. [About this edition](#) answers the question in short, and the Better Continents README, in its section *Upgrading from 0.9: existing worlds and new worlds*, in full.

New worlds

- **World Size lays out the whole world.** A new world's maps span World Size + Edge Size on each side of the centre (older worlds: 21,000 m whatever World Size says); its alt-biome grid covers the world and the game's locations reach its edge; the game's own biome bands, the Ashlands and Deep North rings, and the lakes and stream sources follow World Size, and the minimap follows World Size + Edge Size; the alt-biome *Grid* setting has no effect. With [Expand World Size](#) installed, it lays out the world as before; its World Stretch magnifies the maps of any Better Continents world, and the log warns. The practical maximum is World Size + Edge Size of about 16,350 m. In [Global](#), [Edge Size](#), [Heightmap](#), [Image maps](#), [Alt Biomes](#), the [FAQ](#) and the [Quick Start](#).
- **Heightmap Alpha works.** A 16-bit grey heightmap with a 16-bit alpha blends with the game's own terrain: transparent pixels are the game's terrain. Older worlds keep the old reading with Heightmap Alpha on (8-bit heights, the alpha unused); with it off every world reads 16-bit grey. In [Heightmap](#).
- **Biome precision goes up to 31** (cells of 2 m in a 64 m zone; older worlds stop at 5). In [Biome map](#).
- **Location map pins land exactly on their pixel**, a pin of several pixels on the pixel nearest its middle, locations that share a colour dealt out the same way every time (maps from a world export are read where the export wrote them). The **start position override is placed before the pins**, and **Start Position X and Y** accept −1,000,000 to 1,000,000 m (every world). In [Location map](#) and [Start Position](#).
- **Expand World Data:** its altitude rules (altitude multiplier and delta, water depth, height limits, lava dip) apply over a heightmap's heights; on a world with a biome map and no heat map, its lava biomes are

hot where the biome map puts them; a terrain legend can name its biomes' grounds; biome precision keeps its territories' ground colours; the world saves the names of its added biomes and follows them when the numbering changes. In [Biome map](#) and [Terrain map](#).

- **Compact Maps (experimental, off by default)** keeps a new world's maps compressed in memory and in the world file, with **Map Memory** as the budget for the decoded tiles; Better Continents 0.9 cannot read such a world. In [Export and Import](#) and [Settings](#).

Every world

- **Heightmap Amount 1 is the default everywhere**, the world export's included (it was 2): a heightmap then spans −30 m to 170 m on the game's scale, where the sea is at 30 m (60 m below the water to 140 m above it), and Amount 2 (−30 m to 370 m, up to 340 m above the water) is for ground higher than that. An exported [heightmap.png](#) records its Amount and Sea Level inside the PNG, and a new world that reads it at other values warns in the log; [bc info](#) shows the record. A [BetterContinents.cfg](#) that held the old export default of 2 is set to 1 once. In [Heightmap](#), [Export and Import](#), [Project](#), [Settings](#) and the [FAQ](#).
- **bc h alpha decodes the heightmap again at once**, in every world: an older world re-reads it the old way (8-bit grey, the alpha unused) with Heightmap Alpha on, and as 16-bit grey with it off. Before, a change did nothing until the world was loaded again. In [Heightmap](#).
- **A world export keeps the lava and moss of an Expand World Data biome**. With Expand World Data installed, an export treats an added biome whose terrain is the Ashlands or the Mistlands as that ground for the lava and moss maps, so rebuilding the world paints them again.
- **Doubled vegetation**: in every world made with Better Continents, old ones included, a plant is not placed within 1 m of the same kind of object already standing in its zone, or placed there by another vegetation entry in the same pass. It changes vegetation only, never terrain, and only in zones generated from now on: a zone that is already generated keeps what it has. One entry never blocks itself, so the game's densities and groups stay for every prefab with one entry, except beside an object of that prefab that already stands in its zone (one of a location placed just before, or of an earlier fill); where two entries place the same prefab (a vegetation map's, an alt biome's added vegetation) a second plant within 1 m of the first is dropped, so a zone generated from now on can hold slightly fewer plants than in 0.9.4. [bc_twins](#) (also [bc twins](#)) finds and removes the doubles a world already has. In [Vegetation map](#) and the [FAQ](#).
- **Maps are held as tiles** of 128 × 128 pixels, a tile of one value held as that value: for a real 10,501 px heightmap, forest map and biome map, about 99 MB instead of about 1.32 GB, every value the same. In [Image maps](#).
- **Console tools**: [bc_export](#), [bc_cache](#), [bc_import](#), [bc_altbiomes](#) and [bc_twins](#) answer the admin who ran them on a dedicated server; [bc cache](#) and [bc twins](#) join the [bc tree](#); [bc <group> help](#) lists a group; the console shows the config's defaults and ranges (Heightmap Override All, Forest Scale, Forestmap Add and Start Position had drifted). In [Settings](#).
- **Zones are regenerated by Better Continents**: after each [bc](#) change and on [bc regen](#) (the [bc](#) commands need cheats, which Debug Mode turns on when you spawn), every generated zone of the world is reset and generates again with the new settings when somebody comes near, except zones within one zone of something a player built, a tombstone, ground a player has worked (fields, paths, roads, levelled or dug ground), or you inside a dungeon (the ground around your own character on the surface is regenerated too). A player connected from another machine keeps the zones their game has loaded around them, checked as the work goes. A location that reaches into more than one zone is kept or regenerated whole (the parts of it in a zone nobody has generated yet are cleared with it, so regenerating again leaves no second copy), crops are kept with their field, and a tree grown from a sapling counts as the world's. Players, what players built, tombstones and tamed animals are never removed. The work runs on the machine that runs the world (single player or the host), in a world that

uses Better Continents (a vanilla world is refused with a line that says so), spread over frames, with a start, progress and finish line in the console; a world that is saved while it runs stores the zones it has emptied as not generated and never a location half cleared, a run that starts over finishes the zone it was in, and when an error stops the work the zones it had emptied and left waiting for their neighbours are finished, so they generate again, and the zones it had not reached are as they were: **bc regen** resets them. **Debug Reset Command** is empty by default and runs instead when it holds a console command; a config that held **zones_reset start** is set to empty once, with a line in the log. **bc regen** regenerates the zones without rebuilding the loaded terrain (nothing has changed, so the ground already matches the settings) and does not redraw the minimap or rebuild the alt-biome grid; a **bc change** first rebuilds the loaded terrain, the distant terrain and the grass too, which stalls the game for a second or two, and **bc reset** also redraws the minimap and rebuilds the alt-biome grid. The ground of every zone, the zones that stay included, follows a change: one that lowers the ground under a base leaves it standing in the air (the game breaks a piece that has lost its support a few seconds later) and one that raises it buries it, so make big height changes before you build. In [Debug](#), [Settings](#), the [Quick Start](#), the [Setup Guide](#), the [FAQ](#) and [Alt Biomes](#).

- **Water follows its ground.** A zone's water works out how deep the sea is under it once, when the zone loads, so ground rebuilt in place afterwards (a **bc change**, **bc reset**, or a terrain edit that loads after its zone) could leave a square of sea looking deeper or shallower than the water around it. Each zone's water now takes the depth of its rebuilt ground; a world without Better Continents is left as the game has it. In the [FAQ](#).
- **Alt-biome mode Off** means no alt biomes, not no grid: Valheim builds its biome grid for every world. In [Alt Biomes](#).
- **The edge of the world keeps to each world's own size within one game session.** A world loaded after another of a different World Size used to keep the first world's edge (the ship's push back, the kill zone and the water's edge), and with Map Edge Drop-off off another mod's patching of the same game code could put the edge back at World Size.
- **The log says why a location was not placed.** The game keeps one location per 64 m zone and drops a second with only a short message; the log now says which location holds the zone: an error when the start position override was refused, a warning for a pin of the location map (it used to claim the position was "overridden"). In [Start Position](#) and [Location map](#).
- **Config clean-up:** Fix Water Color and Ocean Channels are gone from the config, and the **bc g fixwatercolor** command with them (worlds keep what they saved); **Spawnmap File** is the creature spawn map and is no longer moved into **Locationmap File** or its **spawnmap.png** renamed; a hidden **Config Version** records one-time changes; a new config selects the preset *Disabled* (its old default, *Vanilla*, named no preset; a config that already holds *Vanilla* keeps it, and a world made with it is made without Better Continents, with an error in the log); every setting has one declaration, so config, console and export agree. In [Global](#), [Spawn map](#), [Location map](#) and [Settings](#).

Corrections to earlier edition text

- **The config is read again whenever it changes** (since BC 0.9.0). The Quick Start, Settings, Heightmap and FAQ pages still said that the file is read once, when the game launches, and that an edit needs a relaunch; they now say what the code does.
- **The biome map legend accepts Expand World Data's biome names** (since BC 0.9.3). The Biome map page still said that only the ten vanilla names are accepted.
- **BC 0.9.0 in play.** The About page said that none of the 0.9.0 features had run in a game; it now says that this was so when the edition first covered them.
- **Forest Scale in the console:** the page said the console shows default 0.5 and range 0 to 1; it shows the config's default (1) and range (0 to 10).

- **Start Position:** the range and the console help are the config's (they showed a range of 0 to 1).
- **What Debug Mode does:** the Debug page said that Debug Mode reveals the full map on respawn, as the setting's own description did. It does not, in 0.9.x either: it turns cheats on when you spawn, shows its banner and adds the settings window (a *Better Continents* button in the Esc menu and on the large map, and Alt+F8 while one of them is open). A **bc** change that redraws the minimap, as most do, is what reveals the map. The config description now says what the setting does.
- **bc on a joined player's machine:** the Settings and Debug pages said that **bc** runs only on the machine that runs the world. It is registered for that machine only, but with Server Devcommands installed any player who has cheats on can run it on their own, where a change reaches only that player's own copy of the settings and the zone regeneration refuses.

The edition

- The edition is now the Valheim 1.0 / Better Continents 0.10.x edition. The *New in BC 0.10* box is drawn in blue; [About this edition](#) explains the boxes.
- The [License](#) page lists the 2, 4 and 5 October 2026 modifications.

BC 0.9.4 update (2026-10-02)

- **A world export loaded through Directory brings its own settings.** When a new world is created with **From Config** and `[00 BetterContinents.Debug] Directory` points at a folder that holds an `export.cfg`, Better Continents 0.9.4 lays that `export.cfg` over `BetterContinents.cfg` for the world, the way an import does. Its settings win; **Directory** stays as the config has it, so a moved or copied export still loads; nothing is written to either file; and the log lists every setting that differs from the config. A folder without `export.cfg` works as before. Before 0.9.4 such a world kept the config's own values: the default Heightmap Amount of 1 left an export's heightmap (stored for Amount 2) almost all under water, and the default forest, location and alt-biome settings gave the wrong forest density, a second set of locations and extra random alt biomes. In [Project](#), [Export and Import](#) and the [FAQ](#).
- The edition gains the *New in BC 0.9.4* box, drawn like the *New in BC 0.9.0* box. [About this edition](#) explains it.

BC 0.9.1 update (2026-09-25)

- Better Continents was rebuilt and re-verified for Valheim 1.0.16. Nothing this guide describes changed in the game or in the mod.
- The edition now names the game as **Valheim 1.0** and the mod as **0.9.x** wherever it states what it covers, so a patch release of either does not need a new guide. The edition boxes are labelled *Updated for Valheim 1.0 / BC 0.8.0* (they were *Updated for Valheim 1.0.15 / BC 0.8.0*); their content is unchanged.

BC 0.9.0 update (2026-09-24)

World export and import

- New chapter [Export and Import](#): `bc_export` writes the loaded world to a folder of maps (heightmap, biome, location, forest, heat, alt-biome, lava, moss and paint maps, plus `export.cfg`, `README.txt` and `manifest.json`); `bc_import` (or a New World preset the export makes automatically) turns such a folder back into a world, either as a preset in the New World dropdown or by copying its settings into `BetterContinents.cfg` (**From Config**).

- A separate, illustrated [BetterContinents-Export-Guide.pdf](#), included in the same package as this guide, walks a newcomer through both. [Export and Import](#) is this guide's own short summary and points to it.
- An in-game **export HUD** (a status box on **F9**, a window with Export and Import tabs on **F7**), turned on by [\[09 BetterContinents.Export\] Hud](#); a server's **Hud** and **Allow Export** settings apply to its connected clients too.

Config that applies while the game runs

- [BetterContinents.cfg](#) is now watched and re-read whenever it changes on disk, not only once when the game launches. A New World's own settings (Heightmap Amount and the rest) still only matter for a world at the moment it is created, but an edit to the file reaches the next world you create in the same session, with no restart. In [Export and Import](#).

Joining a world: transfer rate and the shareable cache

- [\[07 BetterContinents.Misc\] Settings Transfer Rate](#) (Vanilla, KB256, KB384, KB512 (the default), KB768, MB1, MB1_5, MB3, Unlimited): the fixed send rate a host or dedicated server sets on a joining player's connection for the settings download, for that transfer only. Valheim's own rate is about 150 KB/s; Steam has no congestion control, so it sends at exactly the rate set. Only the sending machine's value counts. In [Export and Import](#) and [Settings](#).
- [bc_cache export](#), [bc_cache import <file or folder>](#) and [bc_cache list](#): a world's settings as a shareable [.bcworld](#) file that a player imports before joining, so the join skips the download; a [.bcworld](#) under [BepInEx/plugins/](#) or in [BepInEx/config/BetterContinents/seed/](#) is imported automatically when the game starts. In [Export and Import](#).

Biome precision

- **Biome precision works again** ([\[03 BetterContinents.Biomemap\] Biome precision](#), console [bc b p](#), 0 to 5): from 0 (vanilla: a 64 m terrain zone reads the biome map only at its four corners) to 5 (a corner every 11 m), it sets how closely ground texture, grass, vegetation and spawn points follow your biome map inside the zone. It never changes terrain height, and it never changes how locations or alt biomes are placed, which still use vanilla's four-corner, 12 m rules. In [Biome map](#) and [Export and Import](#).

BC 0.8.1 update (2026-09-22)

Maintenance, install and licence

- Wubarrk now maintains Better Continents: the About page, Introduction, Setup Guide and title page give the Hexium page as the install source and github.com/RGLabs84/BetterContinents10, where each release is tagged, as the source code. The stale references to pull request #9 and to Thunderstore releases were removed.
- The edition now covers BC 0.8.1. *New in BC 0.8.1* boxes mark what 0.8.1 adds or fixes; what the edition says about 0.8.0 also holds for 0.8.1 unless such a box says otherwise. The Quick Start's example of the in-game banner now shows v0.8.1.
- The companion mods now match the Better Continents README: Server Devcommands, Upgrade World, Infinity Hammer and TortalPortal, with the README's links (Introduction, Quick Start and Setup Guide).
- The License page lists this update as a second modification.

Planting alt biomes (Alt Biomes chapter)

- The planned-feature note became the section *Planting alt biomes with colours*: setting up the alt-biome map, the legend, which pixels are planted, the default palette, what planting does (with the quota rule, what happens when planting fails, and multiplayer), the three modes, the controls for random placement with the per-alt-biome overrides and the *Grid* setting, reports and commands (with `bc_altbiomes` for every player), limits, and compatibility.
- Notes about planting and the new controls in the chapter's introduction and in *What this means for map authors*.
- The alt-biome map, its config section `08 BetterContinents.AltBiomes` and its commands were added to the Introduction, Quick Start, Image maps, Project and Settings.

Colour tables and palette

- The default alt-biome palette (32 colours, grouped by base biome, each with the base biomes it plants on) and the *Biome map* colour table are generated from Better Continents' palette file, `palettes/palette.json`. The Biome map table now uses the names of the legend file; the original table's colour chips are shown in *Other images*.
- New Quick Start section *Painting colour maps*: the palette file `BetterContinents.gpl` and the printable chart `altbiome-palette.png` (in the release package and the repository's `palettes/` folder), importing the palette in GIMP and Krita, anti-aliasing off, and exporting without resampling or colour conversion.

The 0.8.1 fixes

- **Expand World Size**: a world smaller than 10,500 m no longer crashes (EWS issue #26), and larger worlds map alt-biome regions correctly. In *Global* and the Alt Biomes chapter.
- **In-game map edits**: map and setting changes made with the `bc` commands (`bc reload ...` and the other `bc` edits) now reach the alt-biome regions and the biomes of terrain chunks, which kept the grid from before the edit until the world was loaded again. In *The cache file*, and noted in Settings (console), Image maps, Biome map and the FAQ.
- **Deep North weather**: the game tested the camera's height instead of the north-south position, so Deep North weather showed at sea in the wrong places on maps with Deep North across the middle. On BC worlds with a biome map it now follows the map, as Ashlands weather already does. In *Biome map*.
- **Land beyond 10,500 m**: on worlds with Map Edge Drop-off off, land past 10,500 m no longer takes the ocean's biome for its terrain, vegetation and spawns. In *Global* and the Alt Biomes chapter.
- **Locations that accept several biomes** no longer search the wrong biome, or one the map lacks. In *Biome map*.
- Guards the game's biome data cache with a fingerprint, so a cache built for other settings is never reused. Valheim 1.0.15 itself no longer reads that cache.

Corrections to earlier edition text

- **Valheim 1.0.15 keeps no stale biome grid**. The earlier text described the biome cache of older Valheim builds (1.0.7 and 1.0.12). Valheim 1.0.15 deletes the cache file and rebuilds the grid on every world load, on the server and on every client, so the advice to delete the cache file by hand is removed. In *The cache file*, and in the notes in Settings, Image maps, Biome map and the FAQ.
- **World Size and Edge Size do not stretch the maps**. On a Better Continents world the image maps always cover the square from -10,500 m to +10,500 m; the World Size setting only moves the edge-of-the-world mechanics. Corrected in *Global*, Image maps, the FAQ and Heightmap.

- **Incompatible alt biomes.** The *Incompatible with* column of the alt-biome table listed an incompatibility only for the alt biome that declares it. It now lists both directions, because the game checks both.
- **Low regions.** A region fails the height rule when the midpoint of its edge heights is below 30 m; at exactly 30 m it passes.
- **Missing console animations.** The two animations that the original pages reference but that were never in the docs repository are no longer marked where they would appear; the references are removed (Location map, Spawn map and Vegetation map), and [Other images](#) says so.

Valheim 1.0.15 / BC 0.8.0 update (2026-09-22)

Whole guide

- Console commands updated from `bc param <group> <setting>` to `bc <group> <setting>`, and renamed groups and subcommands corrected: `fo ad` → `fo add`, the location map `s` → `l`, the spawn map `sm` → `spawn`, the vegetation map `vm` → `vegetation`. Commands that no longer exist are marked (`g ma`, `g oc`, `f fn`, `f bl`, all of `ri`).
- The console animations are captioned as recordings of an older version.
- New pages: About this edition, [License](#), [Height Layers](#), [Alt Biomes](#), this appendix, [Other images](#), and the full text of the [GNU General Public License, version 3](#) as the final appendix.
- The guide is licensed under GPL-3.0. This edition is a modified version by Wubarrk (2026-09-22), under the same license. Its Markdown source and build script are attached to the PDF (see [License](#)).

Introduction

- Sharing a 1.0 world means copying its folder, which holds the extension-less `BetterContinents` file. Version matching between server and clients explained.
- The Flatmap is legacy. Mountains Amount and the ridge settings are gone, replaced by Height Layers. Continent Size only affects the height layers. Where the PNG export command is. New settings and alt biomes pointed to. Links to the Hexium page, the source repository and the companion mods.

Quick Start

- New section *Creating a world with your own maps*: the 1.0.15 workflow, covering the project folder, when the config is read (at launch), the **From Config** preset dropdown, the ENABLED banner, the inspection commands, iterating (maps are baked in, zones reset with Upgrade World), sharing, and presets.
- Built-in presets for worlds without image maps. The template's "spawnmap" is today's location map. Biome colours snap to the nearest legend colour.

Setup Guide

- Installing from the Hexium page (Wubarrk now maintains Better Continents), and the source code link. The companion mods that the Better Continents README recommends (Server Devcommands adds tab completion; Upgrade World resets zones).
- Dedicated server: the 1.0 world folder layout and the extension-less settings file; a dedicated server cannot create a BC world; pre-1.0 worlds are upgraded (old file kept as `.BetterContinents.pre10`); save operations are not yet play-tested.
- Settings are sent to clients and cached; mismatched versions are refused.

FAQ

- `worlds_local` and world folders. BC's log prefix. Images only need to be square (power of two no longer enforced); map scale and orientation.
- New questions: a drowned world, edited images not changing the world, and BC showing DISABLED.

Image maps

- Every map covers the whole square world, top is north, maps are baked at creation, legend files, config sections, and `bc reload`.

Heightmap

- Map scale corrected to 21 km (about 5.1 m per pixel at 4096). 8-bit precision at the default Amount.
- Creation hints corrected: sea level can be calculated; the `#0d0d0d` observation is outdated; the old test settings are no longer needed; rivers and lakes must be carved; keep Meadows central; the centre cap; sanity-checking a map.
- New section *Height scale and the waterline*: the height formula, the waterline at $0.30 / \text{Amount}$, 140 m ceiling, table of values, the 0.15 mistake, Sea Level's effect, and authoring for Amount 1.
- Heightmap Amount is the ceiling and is read at launch. Blend works as a multiplier in the new height function.
- New settings documented: Heightmap Mask, Heightmap Override All, Heightmap Alpha (then without a blend: the heightmap read at 8 bits, the alpha unused).

Flatmap

- Marked as legacy: no config, console command or project file in 0.8.0; replaced by Height Layers.

Roughmap

- Ignored while Heightmap Override All is on. Config section.

Biome map

- Legend file format and default contents. Only the ten vanilla biome names are accepted, so Expand World Data custom biomes can no longer be mapped. Nearest-colour snapping, with a soft coastline becoming a Mistlands fringe. Deep North behaviour follows the map (not yet play-tested). Omitting a biome no longer hangs world creation. Radial layout advice and a link to Alt Biomes. The unshown biome key image added. Biome precision is disabled.

Terrain map, Heat map, Paint map, Lava map, Moss map

- Config names and sections, project file names, console commands, legend files. Terrain colours match exactly.
- Heat map: *heat* > 0 means Ashlands, so heat must be exactly 0 elsewhere on land; a sea ramp is fine; the fallback to the biome map without a heat map; Heatmap Scale (range, and 0 disables).
- Paint map: `paintmap.txt` syntax.

Forest

- Forest Scale's real config default (1) and range (0 to 10), the curve on which 0.5 is vanilla, and values above about 1.15 breaking it.
- Forest Amount 0.5 is neutral. The minimap statement corrected (vanilla overlay only in Meadows, Plains and Black Forest). Which prefabs *Forest Factor Overrides All Trees* affects.
- New section *Recommended forest map settings*: Multiply 0, Add 1, so that a higher value means more trees.

Location map

- The unshown location colour chart added, with its two colours that differ from `locationmap.txt` and the two entries it lacks. Legend syntax. Skip Default Locations (name, section, alt biome locations). The start temple. `bc locs`, `bosses`, `show` and `hide` (and the `hide` gotcha). The legacy spawnmap migration.

Spawn map and Vegetation map

- Legend semantics as implemented: `none`, `+name` enables, `-name` disables, a bare name only exempts from `none`, wildcards, comments, and pure white. The first two spawn map examples corrected. The vegetation legend is `vegetationmap.txt`, not `spawnmap.txt`. Vegetation examples clarified (FirTree is the fir). Raid spawns unaffected.
- The `Spawnmap File` config trap (migrated to Locationmap File when Locationmap File is empty).

Settings

- The Sea Level example's numbers (± 200 m, 20 m per 0.05). When the config is read. The **From Config** dropdown and presets.
- Config file name and section table.
- The console opens with F5; `bc` is a cheat command (`devcommands`, `confirmcheats`) that is registered for the host only; the syntax; true/false; every change regenerates and resets zones; changes are saved with the world.
- New sections: a complete console command reference (with the four recordings the site never showed), and the in-game settings window.

Global

- What applies to new worlds (BC's height function only replaces vanilla's with a heightmap or height layers).
- Enabled only matters with From Config. Continent Size only scales height layers, inversely. Mountains Amount removed. Sea Level: new formula and waterline. Ocean Channels has no effect on new worlds and no console command. Rivers bypassed by heightmaps. Mountains Allowed At Center caps heightmaps near the centre. Booleans are true/false.
- New settings documented: World Size, Edge Size, Ashlands Gap, Deep North Gap, Skip Default Locations, Fix Water Color (no effect yet).

Project

- The setting's config section, file-name lookup from the console, and the complete 0.8.0 file-name list (flatmap.png no longer loaded; spawnmap.png is now the creature spawn map).

Ridges

- Marked as removed in 0.8.0, replaced by the Height Layers' *Ridges* preset.

Start Position

- Coordinates are metres, Y is north–south. Config section. Console commands and their misleading 0-to-1 help text.

Debug

- What Debug Mode does in 0.8.0. Skip Default Locations' new name and section, and that it also skips alt biome locations. New settings documented: Debug Reset Command and Override version.

Minor corrections (not marked in place)

- Start Position X: the range typo '0500 corrected to 10500.
- Setup Guide: the broken link [setup.html](#) corrected to the Client section of the Setup Guide.


Appendix B

Other images

Updated for Valheim 1.0 / BC 0.8.0: This appendix is new in this edition. The original docs repository holds 54 images, all byte-identical to those on the live site. Ten of them are not displayed by any page of the site. This edition shows six of those where they belong:


- `console/bc-help.gif`, `console/bc-info.gif`, `console/bc-clouds.gif` and `console/bc-mapds.gif`, in the [console command reference](#);
- `maps/biome-colors.png`, on the [Biome map](#) page;
- `spawnmap-ref.png`, on the [Location map](#) page.

The remaining four are plain 64 × 64 swatches, shown here for completeness: black, grey, white and the Meadows green.



black.png


gray.png


white.png


meadows.png

The [Biome map](#) page's colour table now shows swatches generated from Better Continents' palette file. The original table's colour chips (`biomes/*.png`) are shown here, with the names and values the original table gave them:

Chip	Original name	Value
	Ocean	#0000FF
	Meadows	#00FF00
	Black Forest	#007F00
	Swamp	#7F7F00
	Mountains	#FFFFFF
	Plains	#FFFF00
	Mistlands	#7F7F7F
	Deep North	#00FFFF
	Ash Lands	#FF0000
	Default	#000000

Two images that the original pages reference, `console/bc-param-s-fn.gif` (Location map and Spawn map) and `console/bc-param-v-fn.gif` (Vegetation map), are not in the repository and return "not found" on the live site. This edition leaves those references out.

Appendix C

GNU General Public License, version 3

The GNU General Public License, version 3, reproduced verbatim from original/LICENSE (identical to updated/LICENSE).

GNU GENERAL PUBLIC LICENSE
Version 3, 29 June 2007

Copyright (C) 2007 Free Software Foundation, Inc. <<https://fsf.org/>>
Everyone is permitted to copy and distribute verbatim copies
of this license document, but changing it is not allowed.

Preamble

The GNU General Public License is a free, copyleft license for software and other kinds of works.

The licenses for most software and other practical works are designed to take away your freedom to share and change the works. By contrast, the GNU General Public License is intended to guarantee your freedom to share and change all versions of a program--to make sure it remains free software for all its users. We, the Free Software Foundation, use the GNU General Public License for most of our software; it applies also to any other work released this way by its authors. You can apply it to your programs, too.

When we speak of free software, we are referring to freedom, not price. Our General Public Licenses are designed to make sure that you have the freedom to distribute copies of free software (and charge for them if you wish), that you receive source code or can get it if you want it, that you can change the software or use pieces of it in new free programs, and that you know you can do these things.

To protect your rights, we need to prevent others from denying you these rights or asking you to surrender the rights. Therefore, you have certain responsibilities if you distribute copies of the software, or if you modify it: responsibilities to respect the freedom of others.

For example, if you distribute copies of such a program, whether gratis or for a fee, you must pass on to the recipients the same freedoms that you received. You must make sure that they, too, receive or can get the source code. And you must show them these terms so they know their rights.

Developers that use the GNU GPL protect your rights with two steps: (1) assert copyright on the software, and (2) offer you this License giving you legal permission to copy, distribute and/or modify it.

For the developers' and authors' protection, the GPL clearly explains that there is no warranty for this free software. For both users' and authors' sake, the GPL requires that modified versions be marked as changed, so that their problems will not be attributed erroneously to authors of previous versions.

Some devices are designed to deny users access to install or run modified versions of the software inside them, although the manufacturer can do so. This is fundamentally incompatible with the aim of protecting users' freedom to change the software. The systematic pattern of such abuse occurs in the area of products for individuals to use, which is precisely where it is most unacceptable. Therefore, we have designed this version of the GPL to prohibit the practice for those products. If such problems arise substantially in other domains, we stand ready to extend this provision to those domains in future versions of the GPL, as needed to protect the freedom of users.

Finally, every program is threatened constantly by software patents. States should not allow patents to restrict development and use of software on general-purpose computers, but in those that do, we wish to avoid the special danger that patents applied to a free program could make it effectively proprietary. To prevent this, the GPL assures that

patents cannot be used to render the program non-free.

The precise terms and conditions for copying, distribution and modification follow.

TERMS AND CONDITIONS

0. Definitions.

"This License" refers to version 3 of the GNU General Public License.

"Copyright" also means copyright-like laws that apply to other kinds of works, such as semiconductor masks.

"The Program" refers to any copyrightable work licensed under this License. Each licensee is addressed as "you". "Licensees" and "recipients" may be individuals or organizations.

To "modify" a work means to copy from or adapt all or part of the work in a fashion requiring copyright permission, other than the making of an exact copy. The resulting work is called a "modified version" of the earlier work or a work "based on" the earlier work.

A "covered work" means either the unmodified Program or a work based on the Program.

To "propagate" a work means to do anything with it that, without permission, would make you directly or secondarily liable for infringement under applicable copyright law, except executing it on a computer or modifying a private copy. Propagation includes copying, distribution (with or without modification), making available to the public, and in some countries other activities as well.

To "convey" a work means any kind of propagation that enables other parties to make or receive copies. Mere interaction with a user through a computer network, with no transfer of a copy, is not conveying.

An interactive user interface displays "Appropriate Legal Notices" to the extent that it includes a convenient and prominently visible feature that (1) displays an appropriate copyright notice, and (2) tells the user that there is no warranty for the work (except to the extent that warranties are provided), that licensees may convey the work under this License, and how to view a copy of this License. If the interface presents a list of user commands or options, such as a menu, a prominent item in the list meets this criterion.

1. Source Code.

The "source code" for a work means the preferred form of the work for making modifications to it. "Object code" means any non-source form of a work.

A "Standard Interface" means an interface that either is an official standard defined by a recognized standards body, or, in the case of interfaces specified for a particular programming language, one that is widely used among developers working in that language.

The "System Libraries" of an executable work include anything, other than the work as a whole, that (a) is included in the normal form of packaging a Major Component, but which is not part of that Major Component, and (b) serves only to enable use of the work with that Major Component, or to implement a Standard Interface for which an implementation is available to the public in source code form. A "Major Component", in this context, means a major essential component (kernel, window system, and so on) of the specific operating system (if any) on which the executable work runs, or a compiler used to produce the work, or an object code interpreter used to run it.

The "Corresponding Source" for a work in object code form means all the source code needed to generate, install, and (for an executable work) run the object code and to modify the work, including scripts to control those activities. However, it does not include the work's System Libraries, or general-purpose tools or generally available free programs which are used unmodified in performing those activities but which are not part of the work. For example, Corresponding Source includes interface definition files associated with source files for

the work, and the source code for shared libraries and dynamically linked subprograms that the work is specifically designed to require, such as by intimate data communication or control flow between those subprograms and other parts of the work.

The Corresponding Source need not include anything that users can regenerate automatically from other parts of the Corresponding Source.

The Corresponding Source for a work in source code form is that same work.

2. Basic Permissions.

All rights granted under this License are granted for the term of copyright on the Program, and are irrevocable provided the stated conditions are met. This License explicitly affirms your unlimited permission to run the unmodified Program. The output from running a covered work is covered by this License only if the output, given its content, constitutes a covered work. This License acknowledges your rights of fair use or other equivalent, as provided by copyright law.

You may make, run and propagate covered works that you do not convey, without conditions so long as your license otherwise remains in force. You may convey covered works to others for the sole purpose of having them make modifications exclusively for you, or provide you with facilities for running those works, provided that you comply with the terms of this License in conveying all material for which you do not control copyright. Those thus making or running the covered works for you must do so exclusively on your behalf, under your direction and control, on terms that prohibit them from making any copies of your copyrighted material outside their relationship with you.

Conveying under any other circumstances is permitted solely under the conditions stated below. Sublicensing is not allowed; section 10 makes it unnecessary.

3. Protecting Users' Legal Rights From Anti-Circumvention Law.

No covered work shall be deemed part of an effective technological measure under any applicable law fulfilling obligations under article 11 of the WIPO copyright treaty adopted on 20 December 1996, or similar laws prohibiting or restricting circumvention of such measures.

When you convey a covered work, you waive any legal power to forbid circumvention of technological measures to the extent such circumvention is effected by exercising rights under this License with respect to the covered work, and you disclaim any intention to limit operation or modification of the work as a means of enforcing, against the work's users, your or third parties' legal rights to forbid circumvention of technological measures.

4. Conveying Verbatim Copies.

You may convey verbatim copies of the Program's source code as you receive it, in any medium, provided that you conspicuously and appropriately publish on each copy an appropriate copyright notice; keep intact all notices stating that this License and any non-permissive terms added in accord with section 7 apply to the code; keep intact all notices of the absence of any warranty; and give all recipients a copy of this License along with the Program.

You may charge any price or no price for each copy that you convey, and you may offer support or warranty protection for a fee.

5. Conveying Modified Source Versions.

You may convey a work based on the Program, or the modifications to produce it from the Program, in the form of source code under the terms of section 4, provided that you also meet all of these conditions:

- a) The work must carry prominent notices stating that you modified it, and giving a relevant date.
- b) The work must carry prominent notices stating that it is

released under this License and any conditions added under section 7. This requirement modifies the requirement in section 4 to "keep intact all notices".

c) You must license the entire work, as a whole, under this License to anyone who comes into possession of a copy. This License will therefore apply, along with any applicable section 7 additional terms, to the whole of the work, and all its parts, regardless of how they are packaged. This License gives no permission to license the work in any other way, but it does not invalidate such permission if you have separately received it.

d) If the work has interactive user interfaces, each must display Appropriate Legal Notices; however, if the Program has interactive interfaces that do not display Appropriate Legal Notices, your work need not make them do so.

A compilation of a covered work with other separate and independent works, which are not by their nature extensions of the covered work, and which are not combined with it such as to form a larger program, in or on a volume of a storage or distribution medium, is called an "aggregate" if the compilation and its resulting copyright are not used to limit the access or legal rights of the compilation's users beyond what the individual works permit. Inclusion of a covered work in an aggregate does not cause this License to apply to the other parts of the aggregate.

6. Conveying Non-Source Forms.

You may convey a covered work in object code form under the terms of sections 4 and 5, provided that you also convey the machine-readable Corresponding Source under the terms of this License, in one of these ways:

a) Convey the object code in, or embodied in, a physical product (including a physical distribution medium), accompanied by the Corresponding Source fixed on a durable physical medium customarily used for software interchange.

b) Convey the object code in, or embodied in, a physical product (including a physical distribution medium), accompanied by a written offer, valid for at least three years and valid for as long as you offer spare parts or customer support for that product model, to give anyone who possesses the object code either (1) a copy of the Corresponding Source for all the software in the product that is covered by this License, on a durable physical medium customarily used for software interchange, for a price no more than your reasonable cost of physically performing this conveying of source, or (2) access to copy the Corresponding Source from a network server at no charge.

c) Convey individual copies of the object code with a copy of the written offer to provide the Corresponding Source. This alternative is allowed only occasionally and noncommercially, and only if you received the object code with such an offer, in accord with subsection 6b.

d) Convey the object code by offering access from a designated place (gratis or for a charge), and offer equivalent access to the Corresponding Source in the same way through the same place at no further charge. You need not require recipients to copy the Corresponding Source along with the object code. If the place to copy the object code is a network server, the Corresponding Source may be on a different server (operated by you or a third party) that supports equivalent copying facilities, provided you maintain clear directions next to the object code saying where to find the Corresponding Source. Regardless of what server hosts the Corresponding Source, you remain obligated to ensure that it is available for as long as needed to satisfy these requirements.

e) Convey the object code using peer-to-peer transmission, provided you inform other peers where the object code and Corresponding Source of the work are being offered to the general public at no charge under subsection 6d.

A separable portion of the object code, whose source code is excluded

from the Corresponding Source as a System Library, need not be included in conveying the object code work.

A "User Product" is either (1) a "consumer product", which means any tangible personal property which is normally used for personal, family, or household purposes, or (2) anything designed or sold for incorporation into a dwelling. In determining whether a product is a consumer product, doubtful cases shall be resolved in favor of coverage. For a particular product received by a particular user, "normally used" refers to a typical or common use of that class of product, regardless of the status of the particular user or of the way in which the particular user actually uses, or expects or is expected to use, the product. A product is a consumer product regardless of whether the product has substantial commercial, industrial or non-consumer uses, unless such uses represent the only significant mode of use of the product.

"Installation Information" for a User Product means any methods, procedures, authorization keys, or other information required to install and execute modified versions of a covered work in that User Product from a modified version of its Corresponding Source. The information must suffice to ensure that the continued functioning of the modified object code is in no case prevented or interfered with solely because modification has been made.

If you convey an object code work under this section in, or with, or specifically for use in, a User Product, and the conveying occurs as part of a transaction in which the right of possession and use of the User Product is transferred to the recipient in perpetuity or for a fixed term (regardless of how the transaction is characterized), the Corresponding Source conveyed under this section must be accompanied by the Installation Information. But this requirement does not apply if neither you nor any third party retains the ability to install modified object code on the User Product (for example, the work has been installed in ROM).

The requirement to provide Installation Information does not include a requirement to continue to provide support service, warranty, or updates for a work that has been modified or installed by the recipient, or for the User Product in which it has been modified or installed. Access to a network may be denied when the modification itself materially and adversely affects the operation of the network or violates the rules and protocols for communication across the network.

Corresponding Source conveyed, and Installation Information provided, in accord with this section must be in a format that is publicly documented (and with an implementation available to the public in source code form), and must require no special password or key for unpacking, reading or copying.

7. Additional Terms.

"Additional permissions" are terms that supplement the terms of this License by making exceptions from one or more of its conditions. Additional permissions that are applicable to the entire Program shall be treated as though they were included in this License, to the extent that they are valid under applicable law. If additional permissions apply only to part of the Program, that part may be used separately under those permissions, but the entire Program remains governed by this License without regard to the additional permissions.

When you convey a copy of a covered work, you may at your option remove any additional permissions from that copy, or from any part of it. (Additional permissions may be written to require their own removal in certain cases when you modify the work.) You may place additional permissions on material, added by you to a covered work, for which you have or can give appropriate copyright permission.

Notwithstanding any other provision of this License, for material you add to a covered work, you may (if authorized by the copyright holders of that material) supplement the terms of this License with terms:

- a) Disclaiming warranty or limiting liability differently from the terms of sections 15 and 16 of this License; or
- b) Requiring preservation of specified reasonable legal notices or author attributions in that material or in the Appropriate Legal

Notices displayed by works containing it; or

c) Prohibiting misrepresentation of the origin of that material, or requiring that modified versions of such material be marked in reasonable ways as different from the original version; or

d) Limiting the use for publicity purposes of names of licensors or authors of the material; or

e) Declining to grant rights under trademark law for use of some trade names, trademarks, or service marks; or

f) Requiring indemnification of licensors and authors of that material by anyone who conveys the material (or modified versions of it) with contractual assumptions of liability to the recipient, for any liability that these contractual assumptions directly impose on those licensors and authors.

All other non-permissive additional terms are considered "further restrictions" within the meaning of section 10. If the Program as you received it, or any part of it, contains a notice stating that it is governed by this License along with a term that is a further restriction, you may remove that term. If a license document contains a further restriction but permits relicensing or conveying under this license, you may add to a covered work material governed by the terms of that license document, provided that the further restriction does not survive such relicensing or conveying.

If you add terms to a covered work in accord with this section, you must place, in the relevant source files, a statement of the additional terms that apply to those files, or a notice indicating where to find the applicable terms.

Additional terms, permissive or non-permissive, may be stated in the form of a separately written license, or stated as exceptions; the above requirements apply either way.

8. Termination.

You may not propagate or modify a covered work except as expressly provided under this license. Any attempt otherwise to propagate or modify it is void, and will automatically terminate your rights under this license (including any patent licenses granted under the third paragraph of section 11).

However, if you cease all violation of this License, then your license from a particular copyright holder is reinstated (a) provisionally, unless and until the copyright holder explicitly and finally terminates your license, and (b) permanently, if the copyright holder fails to notify you of the violation by some reasonable means prior to 60 days after the cessation.

Moreover, your license from a particular copyright holder is reinstated permanently if the copyright holder notifies you of the violation by some reasonable means, this is the first time you have received notice of violation of this license (for any work) from that copyright holder, and you cure the violation prior to 30 days after your receipt of the notice.

Termination of your rights under this section does not terminate the licenses of parties who have received copies or rights from you under this license. If your rights have been terminated and not permanently reinstated, you do not qualify to receive new licenses for the same material under section 10.

9. Acceptance Not Required for Having Copies.

You are not required to accept this license in order to receive or run a copy of the Program. Ancillary propagation of a covered work occurring solely as a consequence of using peer-to-peer transmission to receive a copy likewise does not require acceptance. However, nothing other than this license grants you permission to propagate or modify any covered work. These actions infringe copyright if you do not accept this license. Therefore, by modifying or propagating a covered work, you indicate your acceptance of this license to do so.

10. Automatic Licensing of Downstream Recipients.

Each time you convey a covered work, the recipient automatically receives a license from the original licensors, to run, modify and propagate that work, subject to this License. You are not responsible for enforcing compliance by third parties with this License.

An "entity transaction" is a transaction transferring control of an organization, or substantially all assets of one, or subdividing an organization, or merging organizations. If propagation of a covered work results from an entity transaction, each party to that transaction who receives a copy of the work also receives whatever licenses to the work the party's predecessor in interest had or could give under the previous paragraph, plus a right to possession of the Corresponding Source of the work from the predecessor in interest, if the predecessor has it or can get it with reasonable efforts.

You may not impose any further restrictions on the exercise of the rights granted or affirmed under this License. For example, you may not impose a license fee, royalty, or other charge for exercise of rights granted under this License, and you may not initiate litigation (including a cross-claim or counterclaim in a lawsuit) alleging that any patent claim is infringed by making, using, selling, offering for sale, or importing the Program or any portion of it.

11. Patents.

A "contributor" is a copyright holder who authorizes use under this License of the Program or a work on which the Program is based. The work thus licensed is called the contributor's "contributor version".

A contributor's "essential patent claims" are all patent claims owned or controlled by the contributor, whether already acquired or hereafter acquired, that would be infringed by some manner, permitted by this License, of making, using, or selling its contributor version, but do not include claims that would be infringed only as a consequence of further modification of the contributor version. For purposes of this definition, "control" includes the right to grant patent sublicenses in a manner consistent with the requirements of this License.

Each contributor grants you a non-exclusive, worldwide, royalty-free patent license under the contributor's essential patent claims, to make, use, sell, offer for sale, import and otherwise run, modify and propagate the contents of its contributor version.

In the following three paragraphs, a "patent license" is any express agreement or commitment, however denominated, not to enforce a patent (such as an express permission to practice a patent or covenant not to sue for patent infringement). To "grant" such a patent license to a party means to make such an agreement or commitment not to enforce a patent against the party.

If you convey a covered work, knowingly relying on a patent license, and the Corresponding Source of the work is not available for anyone to copy, free of charge and under the terms of this License, through a publicly available network server or other readily accessible means, then you must either (1) cause the Corresponding Source to be so available, or (2) arrange to deprive yourself of the benefit of the patent license for this particular work, or (3) arrange, in a manner consistent with the requirements of this License, to extend the patent license to downstream recipients. "Knowingly relying" means you have actual knowledge that, but for the patent license, your conveying the covered work in a country, or your recipient's use of the covered work in a country, would infringe one or more identifiable patents in that country that you have reason to believe are valid.

If, pursuant to or in connection with a single transaction or arrangement, you convey, or propagate by procuring conveyance of, a covered work, and grant a patent license to some of the parties receiving the covered work authorizing them to use, propagate, modify or convey a specific copy of the covered work, then the patent license you grant is automatically extended to all recipients of the covered work and works based on it.

A patent license is "discriminatory" if it does not include within the scope of its coverage, prohibits the exercise of, or is conditioned on the non-exercise of one or more of the rights that are

specifically granted under this License. You may not convey a covered work if you are a party to an arrangement with a third party that is in the business of distributing software, under which you make payment to the third party based on the extent of your activity of conveying the work, and under which the third party grants, to any of the parties who would receive the covered work from you, a discriminatory patent license (a) in connection with copies of the covered work conveyed by you (or copies made from those copies), or (b) primarily for and in connection with specific products or compilations that contain the covered work, unless you entered into that arrangement, or that patent license was granted, prior to 28 March 2007.

Nothing in this License shall be construed as excluding or limiting any implied license or other defenses to infringement that may otherwise be available to you under applicable patent law.

12. No Surrender of Others' Freedom.

If conditions are imposed on you (whether by court order, agreement or otherwise) that contradict the conditions of this License, they do not excuse you from the conditions of this License. If you cannot convey a covered work so as to satisfy simultaneously your obligations under this License and any other pertinent obligations, then as a consequence you may not convey it at all. For example, if you agree to terms that obligate you to collect a royalty for further conveying from those to whom you convey the Program, the only way you could satisfy both those terms and this License would be to refrain entirely from conveying the Program.

13. Use with the GNU Affero General Public License.

Notwithstanding any other provision of this License, you have permission to link or combine any covered work with a work licensed under version 3 of the GNU Affero General Public License into a single combined work, and to convey the resulting work. The terms of this License will continue to apply to the part which is the covered work, but the special requirements of the GNU Affero General Public License, section 13, concerning interaction through a network will apply to the combination as such.

14. Revised Versions of this License.

The Free Software Foundation may publish revised and/or new versions of the GNU General Public License from time to time. Such new versions will be similar in spirit to the present version, but may differ in detail to address new problems or concerns.

Each version is given a distinguishing version number. If the Program specifies that a certain numbered version of the GNU General Public License "or any later version" applies to it, you have the option of following the terms and conditions either of that numbered version or of any later version published by the Free Software Foundation. If the Program does not specify a version number of the GNU General Public License, you may choose any version ever published by the Free Software Foundation.

If the Program specifies that a proxy can decide which future versions of the GNU General Public License can be used, that proxy's public statement of acceptance of a version permanently authorizes you to choose that version for the Program.

Later license versions may give you additional or different permissions. However, no additional obligations are imposed on any author or copyright holder as a result of your choosing to follow a later version.

15. Disclaimer of Warranty.

THERE IS NO WARRANTY FOR THE PROGRAM, TO THE EXTENT PERMITTED BY APPLICABLE LAW. EXCEPT WHEN OTHERWISE STATED IN WRITING THE COPYRIGHT HOLDERS AND/OR OTHER PARTIES PROVIDE THE PROGRAM "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESSED OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE. THE ENTIRE RISK AS TO THE QUALITY AND PERFORMANCE OF THE PROGRAM IS WITH YOU. SHOULD THE PROGRAM PROVE DEFECTIVE, YOU ASSUME THE COST OF ALL NECESSARY SERVICING, REPAIR OR CORRECTION.

16. Limitation of Liability.

IN NO EVENT UNLESS REQUIRED BY APPLICABLE LAW OR AGREED TO IN WRITING WILL ANY COPYRIGHT HOLDER, OR ANY OTHER PARTY WHO MODIFIES AND/OR CONVEYS THE PROGRAM AS PERMITTED ABOVE, BE LIABLE TO YOU FOR DAMAGES, INCLUDING ANY GENERAL, SPECIAL, INCIDENTAL OR CONSEQUENTIAL DAMAGES ARISING OUT OF THE USE OR INABILITY TO USE THE PROGRAM (INCLUDING BUT NOT LIMITED TO LOSS OF DATA OR DATA BEING RENDERED INACCURATE OR LOSSES SUSTAINED BY YOU OR THIRD PARTIES OR A FAILURE OF THE PROGRAM TO OPERATE WITH ANY OTHER PROGRAMS), EVEN IF SUCH HOLDER OR OTHER PARTY HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

17. Interpretation of Sections 15 and 16.

If the disclaimer of warranty and limitation of liability provided above cannot be given local legal effect according to their terms, reviewing courts shall apply local law that most closely approximates an absolute waiver of all civil liability in connection with the Program, unless a warranty or assumption of liability accompanies a copy of the Program in return for a fee.

END OF TERMS AND CONDITIONS

How to Apply These Terms to Your New Programs

If you develop a new program, and you want it to be of the greatest possible use to the public, the best way to achieve this is to make it free software which everyone can redistribute and change under these terms.

To do so, attach the following notices to the program. It is safest to attach them to the start of each source file to most effectively state the exclusion of warranty; and each file should have at least the "copyright" line and a pointer to where the full notice is found.

```
<one line to give the program's name and a brief idea of what it does.>
Copyright (C) <year> <name of author>
```

```
This program is free software: you can redistribute it and/or modify
it under the terms of the GNU General Public License as published by
the Free Software Foundation, either version 3 of the License, or
(at your option) any later version.
```

```
This program is distributed in the hope that it will be useful,
but WITHOUT ANY WARRANTY; without even the implied warranty of
MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the
GNU General Public License for more details.
```

```
You should have received a copy of the GNU General Public License
along with this program. If not, see <https://www.gnu.org/licenses/>.
```

Also add information on how to contact you by electronic and paper mail.

If the program does terminal interaction, make it output a short notice like this when it starts in an interactive mode:

```
<program> Copyright (C) <year> <name of author>
This program comes with ABSOLUTELY NO WARRANTY; for details type `show w'.
This is free software, and you are welcome to redistribute it
under certain conditions; type `show c' for details.
```

The hypothetical commands `show w' and `show c' should show the appropriate parts of the General Public License. Of course, your program's commands might be different; for a GUI interface, you would use an "about box".

You should also get your employer (if you work as a programmer) or school, if any, to sign a "copyright disclaimer" for the program, if necessary. For more information on this, and how to apply and follow the GNU GPL, see <https://www.gnu.org/licenses/>.

The GNU General Public License does not permit incorporating your program into proprietary programs. If your program is a subroutine library, you may consider it more useful to permit linking proprietary applications with the library. If this is what you want to do, use the GNU Lesser General Public License instead of this License. But first, please read <https://www.gnu.org/licenses/why-not-lgpl.html>.